
asammdf Documentation

Release "6.3.0.dev24"

Daniel Hrisca

Apr 17, 2021

Contents

1	Introduction	3
1.1	Project goals	3
1.2	Features	3
1.3	Major features not implemented (yet)	4
1.4	Dependencies	5
1.5	Installation	5
1.6	Contributing & Support	6
1.6.1	Contributors	6
2	API	7
2.1	MDF	7
2.2	MDF3	24
2.2.1	MDF version 2 & 3 blocks	31
2.2.1.1	Channel Class	31
2.2.1.2	ChannelConversion Class	33
2.2.1.3	ChannelDependency Class	34
2.2.1.4	ChannelExtension Class	35
2.2.1.5	ChannelGroup Class	35
2.2.1.6	DataGroup Class	36
2.2.1.7	FileIdentificationBlock Class	37
2.2.1.8	HeaderBlock Class	37
2.2.1.9	ProgramBlock Class	38
2.2.1.10	TextBlock Class	39
2.2.1.11	TriggerBlock Class	39
2.3	MDF4	40
2.3.1	MDF version 4 blocks	50
2.3.1.1	AttachmentBlock Class	50
2.3.1.2	Channel Class	51
2.3.1.3	ChannelConversion Class	53
2.3.1.4	ChannelGroup Class	55
2.3.1.5	DataGroup Class	55
2.3.1.6	DataList Class	56
2.3.1.7	DataBlock Class	56
2.3.1.8	FileIdentificationBlock Class	57
2.3.1.9	HeaderBlock Class	57
2.3.1.10	SourceInformation Class	58

2.3.1.11	FileHistory Class	59
2.3.1.12	TextBlock Class	59
2.3.1.13	EventBlock Class	60
2.4	Signal	61
3	Bus logging	65
4	Tips	67
4.1	Selective channel loading	67
4.2	Data coupling	67
4.3	Chunked data access	67
4.4	Optimized methods	67
4.5	Faster file loading	68
4.5.1	Skip XML parsing for MDF4 files	68
5	Examples	69
5.1	Working with MDF	69
5.2	Working with Signal	70
5.3	MF4 demo file generator	71
6	Benchmarks	79
6.1	Test setup	79
6.1.1	Dependencies	79
6.1.2	Usage	79
6.2	x64 Python results	79
6.2.1	Graphical results	81
7	GUI	85
7.1	General shortcuts	85
7.2	Menu	86
7.2.1	File	86
7.2.2	Mode	86
7.2.3	Settings	86
7.2.4	Plot	87
7.3	Single files	88
7.3.1	Layout elements	89
7.3.1.1	1. Opened files tabs	89
7.3.1.2	2. Channel tree display mode	89
7.3.1.3	3. Complete channels tree	90
7.3.1.4	4. Command buttons	90
7.3.1.5	5. Plot/Sub-plots area	91
7.3.1.6	6. Numeric window	91
7.3.1.7	7. Plot window	91
7.3.1.8	8. Sub-plot channel selection list	91
7.3.1.9	9. Sub-plot graphics area	93
7.3.2	Drag & Drop	97
7.4	Multiple files	97
7.5	Comparison	98
8	Indices and tables	99
	Index	101

asammdf is a fast parser/editor for ASAM (Association for Standardisation of Automation and Measuring Systems) MDF (Measurement Data Format) files.

asammdf supports MDF versions 2 (.dat), 3 (.mdf) and 4 (.mf4).

asammdf works on Python ≥ 3.6 (for Python 2.7, 3.4 and 3.5 see the 4.x.y releases)

1.1 Project goals

The main goals for this library are:

- to be faster than the other Python based mdf libraries
- to have clean and easy to understand code base

1.2 Features

- create new mdf files from scratch
- append new channels
- read unsorted MDF v3 and v4 files
- read CAN and LIN bus logging files
- extract CAN and LIN signals from anonymous bus logging measurements
- filter a subset of channels from original mdf file
- cut measurement to specified time interval
- convert to different mdf version
- export to pandas, HDF5, Matlab (v4, v5 and v7.3), CSV and parquet
- merge multiple files sharing the same internal structure
- read and save mdf version 4.10 files containing zipped data blocks
- space optimizations for saved files (no duplicated blocks)
- split large data blocks (configurable size) for mdf version 4
- full support (read, append, save) for the following map types (multidimensional array channels):

- mdf version 3 channels with CDBLOCK
- mdf version 4 structure channel composition
- mdf version 4 channel arrays with CNTemplate storage and one of the array types:
 - * 0 - array
 - * 1 - scaling axis
 - * 2 - look-up
- add and extract attachments for mdf version 4
- handle large files (for example merging two files, each with 14000 channels and 5GB size, on a RaspberryPi)
- extract channel data, master channel and extra channel information as *Signal* objects for unified operations with v3 and v4 files
- time domain operation using the *Signal* class
 - Pandas data frames are good if all the channels have the same time base
 - a measurement will usually have channels from different sources at different rates
 - the *Signal* class facilitates operations with such channels

1.3 Major features not implemented (yet)

- for version 3
 - functionality related to sample reduction block: the sample reduction blocks are simply ignored
- for version 4
 - functionality related to sample reduction block: the sample reduction blocks are simply ignored
 - handling of channel hierarchy: channel hierarchy is ignored
 - full handling of bus logging measurements: currently only CAN and LIN bus logging are implemented with the ability to *get* signals defined in the attached CAN/LIN database (.arxml or .dbc). Signals can also be extracted from an anonymous bus logging measurement by providing a CAN or LIN database (.dbc or .arxml)
 - handling of unfinished measurements (mdf 4): warnings are logged based on the unfinished status flags but no further steps are taken to sanitize the measurement
 - full support for remaining mdf 4 channel arrays types
 - xml schema for MDBLOCK: most metadata stored in the comment blocks will not be available
 - full handling of event blocks: events are transferred to the new files (in case of calling methods that return new *MDF* objects) but no new events can be created
 - channels with default X axis: the default X axis is ignored and the channel group's master channel is used
 - attachment encryption/decryption using user provided encryption/decryption functions; this is not part of the MDF v4 spec and is only supported by this library

1.4 Dependencies

asammdf uses the following libraries

- `numpy` : the heart that makes all tick
- `numexpr` : for algebraic and rational channel conversions
- `wheel` : for installation in virtual environments
- `pandas` : for DataFrame export
- `canmatrix` : to handle CAN/LIN bus logging measurements
- `natsort`
- `lxml` : for canmatrix arxml support
- `lz4` : to speed up the disk IO performance

optional dependencies needed for exports

- `h5py` : for HDF5 export
- `scipy` : for Matlab v4 and v5 .mat export
- `hdf5storage` : for Matlab v7.3 .mat export
- `fastparquet` : for parquet export

other optional dependencies

- `PyQt5` : for GUI tool
- `pyqtgraph` : for GUI tool and Signal plotting (preferably the latest develop branch code)
- `matplotlib` : as fallback for Signal plotting
- `cChardet` : to detect non-standard unicode encodings
- `chardet` : to detect non-standard unicode encodings

1.5 Installation

asammdf is available on

- `github`: <https://github.com/danielhrisca/asammdf/>
- `PyPI`: <https://pypi.org/project/asammdf/>
- `conda-forge`: <https://anaconda.org/conda-forge/asammdf>

```
pip install asammdf
# or for anaconda
conda install -c conda-forge asammdf
```

In case a wheel is not present for your OS/Python versions and you lack the proper compiler setup to compile the c-extension code, then you can simply copy-paste the package code to your site-packages. In this way the python fallback code will be used instead of the compiled c-extension code.

1.6 Contributing & Support

Please have a look over the [contributing guidelines](#)

If you enjoy this library please consider making a donation to the [numpy project](#) or to [danielhrisca](#) using [liberapay](#)

1.6.1 Contributors

Thanks to all who contributed with commits to *asammdf*

- Julien Grave [JulienGrv](#).
- Jed Frey [jed-frey](#).
- Mihai [yahym](#).
- Jack Weinstein [jackjweinstein](#).
- Isuru Fernando [isuruf](#).
- Felix Kohlgrüber [fkohlgrueber](#).
- Stanislav Frolov [stanifrolov](#).
- Thomas Kastl [kasuteru](#).
- venden [venden](#).
- Marat K. [kopytjuk](#).
- freakatzz [freakatzz](#).
- Martin Falch [MartinF](#).
- dxpke [dxpke](#).
- Nick James [driftregion](#).

2.1 MDF

This class acts as a proxy for the *MDF2*, *MDF3* and *MDF4* classes. All attribute access is delegated to the underlying *_mdf* attribute (*MDF2*, *MDF3* or *MDF4* object). See *MDF3* and *MDF4* for available extra methods (*MDF2* and *MDF3* share the same implementation).

An empty MDF file is created if the *name* argument is not provided. If the *name* argument is provided then the file must exist in the filesystem, otherwise an exception is raised.

The best practice is to use the MDF as a context manager. This way all resources are released correctly in case of exceptions.

```
with MDF(r'test.mdf') as mdf_file:
    # do something
```

class `asammdf.mdf.MDF` (*name=None*, *version='4.10'*, *channels=()*, ***kwargs*)

Unified access to MDF v3 and v4 files. Underlying *_mdf*'s attributes and methods are linked to the *MDF* object via *setattr*. This is done to expose them to the user code and for performance considerations.

Parameters

name [string | BytesIO | zipfile.ZipFile | bz2.BZ2File | gzip.GzipFile] mdf file name (if provided it must be a real file name), file-like object or compressed file opened as Python object

Changed in version 6.2.0: added support for zipfile.ZipFile, bz2.BZ2File and gzip.GzipFile

version [string] mdf file version from ('2.00', '2.10', '2.14', '3.00', '3.10', '3.20', '3.30', '4.00', '4.10', '4.11', '4.20'); default '4.10'. This argument is only used for MDF objects created from scratch; for MDF objects created from a file the version is set to file version

channels [iterable] channel names that will be used for selective loading. This can dramatically improve the file loading time.

New in version 6.1.0.

callback (**kwargs) [function] keyword only argument: function to call to update the progress; the function must accept two arguments (the current progress and maximum progress value)

use_display_names (**kwargs) [bool] keyword only argument: for MDF4 files parse the XML channel comment to search for the display name; XML parsing is quite expensive so setting this to *False* can decrease the loading times very much; default *False*

remove_source_from_channel_names (**kwargs) [bool] remove source from channel names ("SpeedXCP3" -> "Speed")

copy_on_get (**kwargs) [bool] copy arrays in the get method; default *True*

expand_zippedfile (**kwargs) [bool] only for bz2.BZ2File and gzip.GzipFile, load the file content into a BytesIO before parsing (avoids the huge performance penalty of doing random reads from the zipped file); default *True*

Examples

```
>>> mdf = MDF(version='3.30') # new MDF object with version 3.30
>>> mdf = MDF('path/to/file.mf4') # MDF loaded from file
>>> mdf = MDF(BytesIO(data)) # MDF from file contents
>>> mdf = MDF(zipfile.ZipFile('data.zip')) # MDF creating using the first valid_
↳MDF from archive
>>> mdf = MDF(bz2.BZ2File('path/to/data.bz2', 'rb')) # MDF from bz2 object
>>> mdf = MDF(gzip.GzipFile('path/to/data.gzip', 'rb')) # MDF from gzip object
```

cleanup_timestamps (minimum, maximum, exp_min=-15, exp_max=15, version=None)
convert *MDF* to other version

New in version 5.22.0.

Parameters

minimum [float] minimum plausible time stamp

maximum [float] maximum plausible time stamp

exp_min (-15) [int] minimum plausible exponent used for the time stamps float values

exp_max (15) [int] maximum plausible exponent used for the time stamps float values

version [str] new mdf file version from ('2.00', '2.10', '2.14', '3.00', '3.10', '3.20', '3.30', '4.00', '4.10', '4.11', '4.20'); default the same as the input file

Returns

out [MDF] new *MDF* object

static concatenate (files, version='4.10', sync=True, add_samples_origin=False, direct_timestamp_continuation=False, **kwargs)
concatenates several files. The files must have the same internal structure (same number of groups, and same channels in each group)

Parameters

files [list | tuple] list of *MDF* file names or *MDF*, zipfile.ZipFile, bz2.BZ2File or gzip.GzipFile instances

..versionchanged:: 6.2.0

added support for zipfile.ZipFile, bz2.BZ2File and gzip.GzipFile

version [str] merged file version

sync [bool] sync the files based on the start of measurement, default *True*

add_samples_origin [bool] option to create a new “__samples_origin” channel that will hold the index of the measurement from where each timestamp originated

direct_timestamp_continuation (False) [bool] the time stamps from the next file will be added right after the last time stamp from the previous file; default *False*

New in version 6.0.0.

kwargs : use_display_names (False) : bool

Returns

concatenate [MDF] new *MDF* object with concatenated channels

Raises

MdfException [if there are inconsistencies between the files]

Examples

```
>>> conc = MDF.concatenate(
    [
        'path/to/file.mf4',
        MDF(BytesIO(data)),
        MDF(zipfile.ZipFile('data.zip')),
        MDF(bz2.BZ2File('path/to/data.bz2', 'rb')),
        MDF(gzip.GzipFile('path/to/data.gzip', 'rb')),
    ],
    version='4.00',
    sync=False,
)
```

convert (*version*)

convert *MDF* to other version

Parameters

version [str] new mdf file version from ('2.00', '2.10', '2.14', '3.00', '3.10', '3.20', '3.30', '4.00', '4.10', '4.11', '4.20'); default '4.10'

Returns

out [MDF] new *MDF* object

cut (*start=None, stop=None, whence=0, version=None, include_ends=True, time_from_zero=False*)

cut *MDF* file. *start* and *stop* limits are absolute values or values relative to the first timestamp depending on the *whence* argument.

Parameters

start [float] start time, default *None*. If *None* then the start of measurement is used

stop [float] stop time, default *None*. If *None* then the end of measurement is used

whence [int] how to search for the start and stop values

- 0 : absolute
- 1 : relative to first timestamp

version [str] new mdf file version from ('2.00', '2.10', '2.14', '3.00', '3.10', '3.20', '3.30', '4.00', '4.10', '4.11', 4.20'); default *None* and in this case the original file version is used

include_ends [bool] include the *start* and *stop* timestamps after cutting the signal. If *start* and *stop* are found in the original timestamps, then the new samples will be computed using interpolation. Default *True*

time_from_zero [bool] start time stamps from 0s in the cut measurement

Returns

out [MDF] new MDF object

export (*fmt*, *filename=None*, ***kwargs*)

export *MDF* to other formats. The *MDF* file name is used is available, else the *filename* argument must be provided.

The *pandas* export option was removed. you should use the method *to_dataframe* instead.

Parameters

fmt [string] can be one of the following:

- *csv* : CSV export that uses the “,” delimiter. This option will generate a new csv file for each data group (<MDFNAME>_DataGroup_<cntr>.csv)
- *hdf5* : HDF5 file output; each *MDF* data group is mapped to a *HDF5* group with the name ‘DataGroup_<cntr>’ (where <cntr> is the index)
- *mat* : Matlab .mat version 4, 5 or 7.3 export. If *single_time_base==False* the channels will be renamed in the mat file to ‘D<cntr>_<channel name>’. The channel group master will be renamed to ‘DM<cntr>_<channel name>’ (<cntr> is the data group index starting from 0)
- *parquet* : export to Apache parquet format

filename [string | pathlib.Path] export file name

****kwargs**

- *single_time_base*: resample all channels to common time base, default *False*
- *raster*: float time raster for resampling. Valid if *single_time_base* is *True*
- *time_from_zero*: adjust time channel to start from 0
- *use_display_names*: use display name instead of standard channel name, if available.
- *empty_channels*: behaviour for channels without samples; the options are *skip* or *zeros*; default is *skip*
- *format*: only valid for *mat* export; can be ‘4’, ‘5’ or ‘7.3’, default is ‘5’
- *oned_as*: only valid for *mat* export; can be ‘row’ or ‘column’
- *keep_arrays* : keep arrays and structure channels as well as the component channels. If *True* this can be very slow. If *False* only the component channels are saved, and their names will be prefixed with the parent channel.
- *reduce_memory_usage* : bool reduce memory usage by converting all float columns to float32 and searching for minimum dtype that can represent the values found in integer columns; default *False*
- *compression* : str compression to be used
 - for *parquet* : “GZIP” or “SNAPPY”

- for `hfd5` : “gzip”, “lzf” or “gzip”
- for `mat` : bool
- `time_as_date` (False) : bool export time as local timezone datetime; only valid for CSV export
New in version 5.8.0.
- `ignore_value2text_conversions` (False) : bool valid only for the channels that have value to text conversions and if `raw=False`. If this is True then the raw numeric values will be used, and the conversion will not be applied.
New in version 5.8.0.
- `raw` (False) : bool export all channels using the raw values
New in version 6.0.0.
- `delimiter` (’,’) : str only valid for CSV: see cpython documentation for `csv.Dialect.delimiter`
New in version 6.2.0.
- `doublequote` (True) : bool only valid for CSV: see cpython documentation for `csv.Dialect.doublequote`
New in version 6.2.0.
- `escapechar` (None) : str only valid for CSV: see cpython documentation for `csv.Dialect.escapechar`
New in version 6.2.0.
- `lineterminator` (“\r\n”) : str only valid for CSV: see cpython documentation for `csv.Dialect.lineterminator`
New in version 6.2.0.
- `quotechar` (”) : str only valid for CSV: see cpython documentation for `csv.Dialect.quotechar`
New in version 6.2.0.
- `quoting` (“MINIMAL”) : str only valid for CSV: see cpython documentation for `csv.Dialect.quoting`. Use the last part of the quoting constant name
New in version 6.2.0.

extract_bus_logging (*database_files*, *version=None*, *ignore_invalid_signals=False*, *consolidated_j1939=True*, *ignore_value2text_conversion=True*)
extract all possible CAN signal using the provided databases.

Changed in version 6.0.0 from *extract_can_logging*

Parameters

- database_files** [dict] each key will contain an iterable of database files for that bus type.
The supported bus types are “CAN”, “LIN”. The iterables will contain the databases as str, `pathlib.Path` or `canamatrix.CanMatrix` objects
Changed in version 6.0.0: added `canmatrix.CanMatrix` type
- version** (None) [str] output file version

ignore_invalid_signals (False) [bool] ignore signals that have all samples equal to their maximum value

New in version 5.7.0.

consolidated_j1939 (True) [bool] handle PGNs from all the messages as a single instance

New in version 5.7.0.

ignore_value2text_conversion (True): bool ignore value to text conversions

New in version 5.23.0.

Returns

mdf [MDF] new MDF file that contains the succesfully extracted signals

Examples

```
>>> "extrac CAN and LIN bus logging"
>>> mdf = asammdf.MDF(r'bus_logging.mf4')
>>> databases = {
...     "CAN": ["file1.dbc", "file2.arxml"],
...     "LIN": ["file3.dbc"],
... }
>>> extracted = mdf.extract_bus_logging(database_files=database_files)
>>> ...
>>> "extrac just LIN bus logging"
>>> mdf = asammdf.MDF(r'bus_logging.mf4')
>>> databases = {
...     "LIN": ["file3.dbc"],
... }
>>> extracted = mdf.extract_bus_logging(database_files=database_files)
```

filter (*channels*, *version=None*)

return new *MDF* object that contains only the channels listed in *channels* argument

Parameters

channels [list] list of items to be filtered; each item can be :

- a channel name string
- (channel name, group index, channel index) list or tuple
- (channel name, group index) list or tuple
- (None, group index, channel index) list or tuple

version [str] new mdf file version from ('2.00', '2.10', '2.14', '3.00', '3.10', '3.20', '3.30', '4.00', '4.10', '4.11', '4.20'); default *None* and in this case the original file version is used

Returns

mdf [MDF] new *MDF* file

Examples

```
>>> from asammdf import MDF, Signal
>>> import numpy as np
>>> t = np.arange(5)
>>> s = np.ones(5)
>>> mdf = MDF()
>>> for i in range(4):
...     sigs = [Signal(s*(i*10+j), t, name='SIG') for j in range(1,4)]
...     mdf.append(sigs)
...
>>> filtered = mdf.filter(['SIG', ('SIG', 3, 1)], ['SIG', 2], (None, 1, 2))
>>> for gp_nr, ch_nr in filtered.channels_db['SIG']:
...     print(filtered.get(group=gp_nr, index=ch_nr))
...
<Signal SIG:
  samples=[ 1.  1.  1.  1.  1.]
  timestamps=[0 1 2 3 4]
  unit=""
  info=None
  comment="">
<Signal SIG:
  samples=[ 31.  31.  31.  31.  31.]
  timestamps=[0 1 2 3 4]
  unit=""
  info=None
  comment="">
<Signal SIG:
  samples=[ 21.  21.  21.  21.  21.]
  timestamps=[0 1 2 3 4]
  unit=""
  info=None
  comment="">
<Signal SIG:
  samples=[ 12.  12.  12.  12.  12.]
  timestamps=[0 1 2 3 4]
  unit=""
  info=None
  comment="">
```

get_group (*index*, *channels=None*, *raster=None*, *time_from_zero=True*, *empty_channels='skip'*, *keep_arrays=False*, *use_display_names=False*, *time_as_date=False*, *reduce_memory_usage=False*, *raw=False*, *ignore_value2text_conversions=False*, *only_basenames=False*)

get channel group as pandas DataFrames. If there are multiple occurrences for the same channel name, then a counter will be used to make the names unique (<original_name>_<counter>)

Parameters

index [int] channel group index

use_display_names [bool] use display name instead of standard channel name, if available.

reduce_memory_usage [bool] reduce memory usage by converting all float columns to float32 and searching for minimum dtype that can represent the values found in integer columns; default *False*

raw (False) [bool] the dataframe will contain the raw channel values

New in version 5.7.0.

ignore_value2text_conversions (False) [bool] valid only for the channels that have value to text conversions and if *raw=False*. If this is *True* then the raw numeric values will be used, and the conversion will not be applied.

New in version 5.8.0.

keep_arrays (False) [bool] keep arrays and structure channels as well as the component channels. If *True* this can be very slow. If *False* only the component channels are saved, and their names will be prefixed with the parent channel.

New in version 5.8.0.

empty_channels ("skip") [str] behaviour for channels without samples; the options are *skip* or *zeros*; default is *skip*

New in version 5.8.0.

only_basenames (False) [bool] use just the field names, without prefix, for structures and channel arrays

New in version 5.13.0.

raster [float | np.array | str] new raster that can be

- a float step value
- a channel name who's timestamps will be used as raster (starting with asammdf 5.5.0)
- an array (starting with asammdf 5.5.0)

see *resample* for examples of using this argument

Returns

df [pandas.DataFrame]

iter_channels (*skip_master=True, copy_master=True*)

generator that yields a *Signal* for each non-master channel

Parameters

skip_master [bool] do not yield master channels; default *True*

copy_master [bool] copy master for each yielded channel

iter_get (*name=None, group=None, index=None, raster=None, samples_only=False, raw=False*)

iterator over a channel

This is usefull in case of large files with a small number of channels.

If the *raster* keyword argument is not *None* the output is interpolated accordingly

Parameters

name [string] name of channel

group [int] 0-based group index

index [int] 0-based channel index

raster [float] time raster in seconds

samples_only [bool]

if *True* return only the channel samples as numpy array; if *False* return a *Signal* object

raw [bool] return channel samples without applying the conversion rule; default *False*

iter_groups (*raster=None, time_from_zero=True, empty_channels='skip', keep_arrays=False, use_display_names=False, time_as_date=False, reduce_memory_usage=False, raw=False, ignore_value2text_conversions=False, only_basenames=False*)

generator that yields channel groups as pandas DataFrames. If there are multiple occurrences for the same channel name inside a channel group, then a counter will be used to make the names unique (<original_name>_<counter>)

Parameters

use_display_names [bool] use display name instead of standard channel name, if available.

New in version 5.21.0.

reduce_memory_usage [bool] reduce memory usage by converting all float columns to float32 and searching for minimum dtype that can represent the values found in integer columns; default *False*

New in version 5.21.0.

raw (False) [bool] the dataframe will contain the raw channel values

New in version 5.21.0.

ignore_value2text_conversions (False) [bool] valid only for the channels that have value to text conversions and if *raw=False*. If this is *True* then the raw numeric values will be used, and the conversion will not be applied.

New in version 5.21.0.

keep_arrays (False) [bool] keep arrays and structure channels as well as the component channels. If *True* this can be very slow. If *False* only the component channels are saved, and their names will be prefixed with the parent channel.

New in version 5.21.0.

empty_channels ("skip") [str] behaviour for channels without samples; the options are *skip* or *zeros*; default is *skip*

New in version 5.21.0.

only_basenames (False) [bool] use just the field names, without prefix, for structures and channel arrays

New in version 5.21.0.

raster [float | np.array | str] new raster that can be

- a float step value
- a channel name whose timestamps will be used as raster (starting with asammdf 5.5.0)
- an array (starting with asammdf 5.5.0)

see *resample* for examples of using this argument

New in version 5.21.0.

```

iter_to_dataframe (channels=None, raster=None, time_from_zero=True,
                    empty_channels='skip', keep_arrays=False, use_display_names=False,
                    time_as_date=False, reduce_memory_usage=False, raw=False,
                    ignore_value2text_conversions=False, use_interpolation=True,
                    only_basenames=False, chunk_ram_size=209715200, interpo-
                    late_outwards_with_nan=False)

```

generator that yields pandas DataFrame's that should not exceed 200MB of RAM

New in version 5.15.0.

Parameters

channels [list] list of items to be filtered (default None); each item can be :

- a channel name string
- (channel name, group index, channel index) list or tuple
- (channel name, group index) list or tuple
- (None, group index, channel index) list or tuple

raster [float | np.array | str] new raster that can be

- a float step value
- a channel name who's timestamps will be used as raster (starting with asammdf 5.5.0)
- an array (starting with asammdf 5.5.0)

see *resample* for examples of using this argument

time_from_zero [bool] adjust time channel to start from 0; default *True*

empty_channels [str] behaviour for channels without samples; the options are *skip* or *zeros*; default is *skip*

use_display_names [bool] use display name instead of standard channel name, if available.

keep_arrays [bool] keep arrays and structure channels as well as the component channels. If *True* this can be very slow. If *False* only the component channels are saved, and their names will be prefixed with the parent channel.

time_as_date [bool] the dataframe index will contain the datetime timestamps according to the measurement start time; default *False*. If *True* then the argument *time_from_zero* will be ignored.

reduce_memory_usage [bool] reduce memory usage by converting all float columns to float32 and searching for minimum dtype that can represent the values found in integer columns; default *False*

raw (False) [bool] the columns will contain the raw values

ignore_value2text_conversions (False) [bool] valid only for the channels that have value to text conversions and if *raw=False*. If this is *True* then the raw numeric values will be used, and the conversion will not be applied.

use_interpolation (True) [bool] option to perform interpolations when multiple timestamp raster are present. If *False* then dataframe columns will be automatically filled with NaN's were the dataframe index values are not found in the current column's timestamps

only_basenames (**False**) [bool] use jsut the field names, without prefix, for structures and channel arrays

interpolate_outwards_with_nan [bool] use NaN values for the samples that lie outside of the original signal's timestamps

chunk_ram_size [int] desired data frame RAM usage in bytes; default 200 MB

Returns

dataframe [pandas.DataFrame] yields pandas DataFrame's that should not exceed 200MB of RAM

resample (*raster*, *version=None*, *time_from_zero=False*)

resample all channels using the given raster. See *configure* to select the interpolation method for interger channels

Parameters

raster [float | np.array | str] new raster that can be

- a float step value
- a channel name who's timestamps will be used as raster (starting with asammdf 5.5.0)
- an array (starting with asammdf 5.5.0)

version [str] new mdf file version from ('2.00', '2.10', '2.14', '3.00', '3.10', '3.20', '3.30', '4.00', '4.10', '4.11', '4.20'); default *None* and in this case the original file version is used

time_from_zero [bool] start time stamps from 0s in the cut measurement

Returns

mdf [MDF] new *MDF* with resampled channels

Examples

```
>>> from asammdf import MDF, Signal
>>> import numpy as np
>>> mdf = MDF()
>>> sig = Signal(name='S1', samples=[1,2,3,4], timestamps=[1,2,3,4])
>>> mdf.append(sig)
>>> sig = Signal(name='S2', samples=[1,2,3,4], timestamps=[1.1, 3.5, 3.7, 3.
→9])
>>> mdf.append(sig)
>>> resampled = mdf.resample(raster=0.1)
>>> resampled.select(['S1', 'S2'])
[<Signal S1:
    samples=[1 1 1 1 1 1 1 1 1 1 2 2 2 2 2 2 2 2 2 2 3 3 3 3 3 3 3 3 3
→4]
    timestamps=[1.  1.1 1.2 1.3 1.4 1.5 1.6 1.7 1.8 1.9 2.  2.1 2.2 2.3
→2.4 2.5 2.6 2.7
2.8 2.9 3.  3.1 3.2 3.3 3.4 3.5 3.6 3.7 3.8 3.9 4. ]
    invalidation_bits=None
    unit=""
    conversion=None
    source=Source(name='Python', path='Python', comment='', source_
→type=4, bus_type=0)
```

(continues on next page)

(continued from previous page)

```

        comment=""
        mastermeta="('time', 1)"
        raw=True
        display_name=
        attachment=()>
, <Signal S2:
    samples=[1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 2 2 3 3 4_
→4]
    timestamps=[1.  1.1 1.2 1.3 1.4 1.5 1.6 1.7 1.8 1.9 2.  2.1 2.2 2.3_
→2.4 2.5 2.6 2.7
2.8 2.9 3.  3.1 3.2 3.3 3.4 3.5 3.6 3.7 3.8 3.9 4. ]
    invalidation_bits=None
    unit=""
    conversion=None
    source=Source(name='Python', path='Python', comment='', source_
→type=4, bus_type=0)
    comment=""
    mastermeta="('time', 1)"
    raw=True
    display_name=
    attachment=()>
]
>>> resampled = mdf.resample(raster='S2')
>>> resampled.select(['S1', 'S2'])
[<Signal S1:
    samples=[1 3 3 3]
    timestamps=[1.1 3.5 3.7 3.9]
    invalidation_bits=None
    unit=""
    conversion=None
    source=Source(name='Python', path='Python', comment='', source_
→type=4, bus_type=0)
    comment=""
    mastermeta="('time', 1)"
    raw=True
    display_name=
    attachment=()>
, <Signal S2:
    samples=[1 2 3 4]
    timestamps=[1.1 3.5 3.7 3.9]
    invalidation_bits=None
    unit=""
    conversion=None
    source=Source(name='Python', path='Python', comment='', source_
→type=4, bus_type=0)
    comment=""
    mastermeta="('time', 1)"
    raw=True
    display_name=
    attachment=()>
]
>>> resampled = mdf.resample(raster=[1.9, 2.0, 2.1])
>>> resampled.select(['S1', 'S2'])
[<Signal S1:
    samples=[1 2 2]
    timestamps=[1.9 2.  2.1]
    invalidation_bits=None

```

(continues on next page)

(continued from previous page)

```

        unit=""
        conversion=None
        source=Source(name='Python', path='Python', comment='', source_
→type=4, bus_type=0)
        comment=""
        mastermeta="('time', 1)"
        raw=True
        display_name=
        attachment=()>
, <Signal S2:
    samples=[1 1 1]
    timestamps=[1.9 2.  2.1]
    invalidation_bits=None
    unit=""
    conversion=None
    source=Source(name='Python', path='Python', comment='', source_
→type=4, bus_type=0)
    comment=""
    mastermeta="('time', 1)"
    raw=True
    display_name=
    attachment=()>
]
>>> resampled = mdf.resample(raster='S2', time_from_zero=True)
>>> resampled.select(['S1', 'S2'])
[<Signal S1:
    samples=[1 3 3 3]
    timestamps=[0.  2.4 2.6 2.8]
    invalidation_bits=None
    unit=""
    conversion=None
    source=Source(name='Python', path='Python', comment='', source_
→type=4, bus_type=0)
    comment=""
    mastermeta="('time', 1)"
    raw=True
    display_name=
    attachment=()>
, <Signal S2:
    samples=[1 2 3 4]
    timestamps=[0.  2.4 2.6 2.8]
    invalidation_bits=None
    unit=""
    conversion=None
    source=Source(name='Python', path='Python', comment='', source_
→type=4, bus_type=0)
    comment=""
    mastermeta="('time', 1)"
    raw=True
    display_name=
    attachment=()>
]
```

static scramble (*name*, *skip_attachments=False*, ***kwargs*)
 scramble text blocks and keep original file structure

Parameters

name [str | pathlib.Path] file name

skip_attachments [bool] skip scrambling of attachments data if True

New in version 5.9.0.

Returns

name [str] scrambled file name

select (*channels*, *record_offset=0*, *raw=False*, *copy_master=True*, *ignore_value2text_conversions=False*, *record_count=None*, *validate=False*)
retrieve the channels listed in *channels* argument as *Signal* objects

Note: the *dataframe* argument was removed in version 5.8.0 use the *to_dataframe* method instead

Parameters

channels [list] list of items to be filtered; each item can be :

- a channel name string
- (channel name, group index, channel index) list or tuple
- (channel name, group index) list or tuple
- (None, group index, channel index) list or tuple

record_offset [int] record number offset; optimization to get the last part of signal samples

raw [bool] get raw channel samples; default *False*

copy_master [bool] option to get a new timestamps array for each selected *Signal* or to use a shared array for channels of the same channel group; default *True*

ignore_value2text_conversions (False) [bool] valid only for the channels that have value to text conversions and if *raw=False*. If this is *True* then the raw numeric values will be used, and the conversion will not be applied.

New in version 5.8.0.

validate (False) [bool] consider the invalidation bits

New in version 5.16.0.

Returns

signals [list] list of *Signal* objects based on the input channel list

Examples

```
>>> from asammdf import MDF, Signal
>>> import numpy as np
>>> t = np.arange(5)
>>> s = np.ones(5)
>>> mdf = MDF()
>>> for i in range(4):
...     sigs = [Signal(s*(i*10+j), t, name='SIG') for j in range(1,4)]
...     mdf.append(sigs)
... 
```

(continues on next page)

(continued from previous page)

```

>>> # select SIG group 0 default index 1 default, SIG group 3 index 1, SIG_
↳ group 2 index 1 default and channel index 2 from group 1
...
>>> mdf.select(['SIG', ('SIG', 3, 1), ['SIG', 2], (None, 1, 2)])
[<Signal SIG:
    samples=[ 1.  1.  1.  1.  1.]
    timestamps=[0 1 2 3 4]
    unit=""
    info=None
    comment="">
, <Signal SIG:
    samples=[ 31.  31.  31.  31.  31.]
    timestamps=[0 1 2 3 4]
    unit=""
    info=None
    comment="">
, <Signal SIG:
    samples=[ 21.  21.  21.  21.  21.]
    timestamps=[0 1 2 3 4]
    unit=""
    info=None
    comment="">
, <Signal SIG:
    samples=[ 12.  12.  12.  12.  12.]
    timestamps=[0 1 2 3 4]
    unit=""
    info=None
    comment="">
]

```

static stack (*files*, *version='4.10'*, *sync=True*, ***kwargs*)

stack several files and return the stacked *MDF* object

Parameters

files [list | tuple] list of *MDF* file names or *MDF*, *zipfile.ZipFile*, *bz2.BZ2File* or *gzip.GzipFile* instances

..versionchanged:: 6.2.0

added support for *zipfile.ZipFile*, *bz2.BZ2File* and *gzip.GzipFile*

version [str] merged file version

sync [bool] sync the files based on the start of measurement, default *True*

kwargs : *use_display_names* (False) : bool

Returns

stacked [*MDF*] new *MDF* object with stacked channels

Examples

```

>>> stacked = MDF.stack(
    [
        'path/to/file.mf4',
        MDF(BytesIO(data)),
    ]
)

```

(continues on next page)

(continued from previous page)

```

MDF(zipfile.ZipFile('data.zip')),
MDF(bz2.BZ2File('path/to/data.bz2', 'rb')),
MDF(gzip.GzipFile('path/to/data.gzip', 'rb')),
],
version='4.00',
sync=False,
)

```

start_time

getter and setter the measurement start timestamp

Returns**timestamp** [datetime.datetime] start timestamp

to_dataframe (*channels=None*, *raster=None*, *time_from_zero=True*, *empty_channels='skip'*,
keep_arrays=False, *use_display_names=False*, *time_as_date=False*, *re-*
duce_memory_usage=False, *raw=False*, *ignore_value2text_conversions=False*,
use_interpolation=True, *only_basenames=False*, *interpo-*
late_outwards_with_nan=False)
generate pandas DataFrame

Parameters**channels** [list] list of items to be filtered (default None); each item can be :

- a channel name string
- (channel name, group index, channel index) list or tuple
- (channel name, group index) list or tuple
- (None, group index, channel index) list or tuple

raster [float | np.array | str] new raster that can be

- a float step value
- a channel name who's timestamps will be used as raster (starting with asammdf 5.5.0)
- an array (starting with asammdf 5.5.0)

see *resample* for examples of using this argument**time_from_zero** [bool] adjust time channel to start from 0; default *True***empty_channels** [str] behaviour for channels without samples; the options are *skip* or *zeros*; default is *skip***use_display_names** [bool] use display name instead of standard channel name, if available.**keep_arrays** [bool] keep arrays and structure channels as well as the component channels. If *True* this can be very slow. If *False* only the component channels are saved, and their names will be prefixed with the parent channel.**time_as_date** [bool] the dataframe index will contain the datetime timestamps according to the measurement start time; default *False*. If *True* then the argument *time_from_zero* will be ignored.

reduce_memory_usage [bool] reduce memory usage by converting all float columns to float32 and searching for minimum dtype that can represent the values found in integer columns; default *False*

raw (False) [bool] the columns will contain the raw values

New in version 5.7.0.

ignore_value2text_conversions (False) [bool] valid only for the channels that have value to text conversions and if *raw=False*. If this is *True* then the raw numeric values will be used, and the conversion will not be applied.

New in version 5.8.0.

use_interpolation (True) [bool] option to perform interpolations when multiple timestamps raster are present. If *False* then dataframe columns will be automatically filled with NaN's were the dataframe index values are not found in the current column's timestamps

New in version 5.11.0.

only_basenames (False) [bool] use just the field names, without prefix, for structures and channel arrays

New in version 5.13.0.

interpolate_outwards_with_nan [bool] use NaN values for the samples that lie outside of the original signal's timestamps

New in version 5.15.0.

Returns

dataframe [pandas.DataFrame]

whereis (*channel*, *source_name=None*, *source_path=None*, *acq_name=None*)
get occurrences of channel name in the file

Parameters

channel [str] channel name string

source_name (None) [str] filter occurrences on source name

source_path (None) [str] filter occurrences on source path

acq_name (None) [str] filter occurrences on channel group acquisition name

New in version 6.0.0.

Returns

occurrences [tuple]

Examples

```
>>> mdf = MDF(file_name)
>>> mdf.whereis('VehicleSpeed') # "VehicleSpeed" exists in the file
((1, 2), (2, 4))
>>> mdf.whereis('VehicleSPD') # "VehicleSPD" doesn't exist in the file
()
```

2.2 MDF3

class `asammdf.blocks.mdf_v3.MDF3` (*name=None*, *version='3.30'*, *channels=()*, ***kwargs*)

The *header* attribute is a *HeaderBlock*.

The *groups* attribute is a list of dicts, each one with the following keys

- *data_group* - *DataGroup* object
- *channel_group* - *ChannelGroup* object
- *channels* - list of *Channel* objects with the same order as found in the mdf file
- *channel_dependencies* - list of *ChannelArrayBlock* in case of channel arrays; list of *Channel* objects in case of structure channel composition
- *data_block* - address of data block
- *data_location* - integer code for data location (original file, temporary file or memory)
- *data_block_addr* - list of raw samples starting addresses
- *data_block_type* - list of codes for data block type
- *data_block_size* - list of raw samples block size
- *sorted* - sorted indicator flag
- *record_size* - dict that maps record ID's to record sizes in bytes
- *size* - total size of data block for the current group
- *trigger* - *Trigger* object for current group

Parameters

name [string | `pathlib.Path`] mdf file name (if provided it must be a real file name) or file-like object

version [string] mdf file version ('2.00', '2.10', '2.14', '3.00', '3.10', '3.20' or '3.30'); default '3.30'

callback [function] keyword only argument: function to call to update the progress; the function must accept two arguments (the current progress and maximum progress value)

Attributes

attachments [list] list of file attachments

channels_db [dict] used for fast channel access by name; for each name key the value is a list of (group index, channel index) tuples

groups [list] list of data group dicts

header [*HeaderBlock*] mdf file header

identification [*FileIdentificationBlock*] mdf file start block

last_call_info [dict | None] a dict to hold information about the last called method.

New in version 5.12.0.

masters_db [dict]

used for fast master channel access; for each group index key the value is the master channel index

memory [str] memory optimization option

name [string] mdf file name

version [str] mdf version

add_trigger (*group, timestamp, pre_time=0, post_time=0, comment=""*)

add trigger to data group

Parameters

group [int] group index

timestamp [float] trigger time

pre_time [float] trigger pre time; default 0

post_time [float] trigger post time; default 0

comment [str] trigger comment

append (*signals, acq_name=None, acq_source=None, comment='Python', common_timebase=False, units=None*)

Appends a new data group.

For channel dependencies type Signals, the *samples* attribute must be a `numpy.recarray`

Parameters

signals [list | `Signal` | `pandas.DataFrame`] list of *Signal* objects, or a single *Signal* object, or a `pandas DataFrame` object. All bytes columns in the `pandas DataFrame` must be *latin-1* encoded

acq_name [str] channel group acquisition name

acq_source [Source] channel group acquisition source

comment [str] channel group comment; default 'Python'

common_timebase [bool] flag to hint that the signals have the same timebase. Only set this if you know for sure that all appended channels share the same time base

units [dict] will contain the signal units mapped to the signal names when appending a `pandas DataFrame`

Examples

```
>>> # case 1 conversion type None
>>> s1 = np.array([1, 2, 3, 4, 5])
>>> s2 = np.array([-1, -2, -3, -4, -5])
>>> s3 = np.array([0.1, 0.04, 0.09, 0.16, 0.25])
>>> t = np.array([0.001, 0.002, 0.003, 0.004, 0.005])
>>> names = ['Positive', 'Negative', 'Float']
>>> units = ['+', '-', '.f']
>>> info = {}
>>> s1 = Signal(samples=s1, timestamps=t, unit='+', name='Positive')
>>> s2 = Signal(samples=s2, timestamps=t, unit='-', name='Negative')
>>> s3 = Signal(samples=s3, timestamps=t, unit='flts', name='Floats')
>>> mdf = MDF3('new.mdf')
>>> mdf.append([s1, s2, s3], comment='created by asammdf v1.1.0')
>>> # case 2: VTAB conversions from channels inside another file
>>> mdf1 = MDF3('in.mdf')
>>> ch1 = mdf1.get("Channel1_VTAB")
```

(continues on next page)

(continued from previous page)

```

>>> ch2 = mdf1.get("Channel2_VTABR")
>>> sigs = [ch1, ch2]
>>> mdf2 = MDF3('out.mdf')
>>> mdf2.append(sigs, comment='created by asammdf v1.1.0')
>>> df = pd.DataFrame.from_dict({'s1': np.array([1, 2, 3, 4, 5]), 's2': np.
    ↳ array([-1, -2, -3, -4, -5])})
>>> units = {'s1': 'V', 's2': 'A'}
>>> mdf2.append(df, units=units)

```

close()

if the MDF was created with `memory='minimum'` and new channels have been appended, then this must be called just before the object is not used anymore to clean-up the temporary file

configure (*, *from_other=None*, *read_fragment_size=None*, *write_fragment_size=None*, *use_display_names=None*, *single_bit_uint_as_bool=None*, *integer_interpolation=None*, *copy_on_get=None*, *float_interpolation=None*, *raise_on_multiple_occurrences=None*)
configure MDF parameters

The default values for the options are the following: * `read_fragment_size = 0` * `write_fragment_size = 4MB` * `use_display_names = False` * `single_bit_uint_as_bool = False` * `integer_interpolation = 0` (ffill - use previous sample) * `float_interpolation = 1` (linear interpolation) * `copy_on_get = False` * `raise_on_multiple_occurrences = True`

Parameters

read_fragment_size [int] size hint of split data blocks, default 8MB; if the initial size is smaller, then no data list is used. The actual split size depends on the data groups' records size

write_fragment_size [int] size hint of split data blocks, default 4MB; if the initial size is smaller, then no data list is used. The actual split size depends on the data groups' records size. Maximum size is 4MB to ensure compatibility with CANape

use_display_names [bool] search for display name in the Channel XML comment

single_bit_uint_as_bool [bool] return single bit channels are np.bool arrays

integer_interpolation [int] interpolation mode for integer channels:

- 0 - repeat previous sample
- 1 - use linear interpolation
- 2 - hybrid interpolation: channels with integer data type (raw values) that have a conversion that outputs float values will use linear interpolation, otherwise the previous sample is used

Changed in version 6.2.0: added hybrid mode interpolation

copy_on_get [bool] copy arrays in the get method

float_interpolation [int] interpolation mode for float channels:

- 0 - repeat previous sample
- 1 - use linear interpolation

New in version 6.2.0.

raise_on_multiple_occurrences [bool] raise exception when there are multiple channel occurrences in the file and the `get` call is ambiguous; default True

New in version 6.2.0.

from_other [MDF] copy configuration options from other MDF

New in version 6.2.0.

extend (*index*, *signals*)

Extend a group with new samples. *signals* contains (values, invalidation_bits) pairs for each extended signal. Since MDF3 does not support invalidation bits, the second item of each pair must be None. The first pair is the master channel's pair, and the next pairs must respect the same order in which the signals were appended. The samples must have raw or physical values according to the *Signals* used for the initial append.

Parameters

index [int] group index

signals [list] list of (numpy.ndarray, None) objects

Examples

```
>>> # case 1 conversion type None
>>> s1 = np.array([1, 2, 3, 4, 5])
>>> s2 = np.array([-1, -2, -3, -4, -5])
>>> s3 = np.array([0.1, 0.04, 0.09, 0.16, 0.25])
>>> t = np.array([0.001, 0.002, 0.003, 0.004, 0.005])
>>> names = ['Positive', 'Negative', 'Float']
>>> units = ['+', '-', '.f']
>>> s1 = Signal(samples=s1, timestamps=t, unit='+', name='Positive')
>>> s2 = Signal(samples=s2, timestamps=t, unit='-', name='Negative')
>>> s3 = Signal(samples=s3, timestamps=t, unit='flts', name='Floats')
>>> mdf = MDF3('new.mdf')
>>> mdf.append([s1, s2, s3], comment='created by asammdf v1.1.0')
>>> t = np.array([0.006, 0.007, 0.008, 0.009, 0.010])
>>> mdf2.extend(0, [(t, None), (s1.samples, None), (s2.samples, None), (s3.
→samples, None)])
```

get (*name=None*, *group=None*, *index=None*, *raster=None*, *samples_only=False*, *data=None*, *raw=False*, *ignore_invalidation_bits=False*, *record_offset=0*, *record_count=None*)

Gets channel samples. Channel can be specified in two ways:

- using the first positional argument *name*
 - if there are multiple occurrences for this channel then the *group* and *index* arguments can be used to select a specific group.
 - if there are multiple occurrences for this channel and either the *group* or *index* arguments is None then a warning is issued
- using the group number (keyword argument *group*) and the channel number (keyword argument *index*). Use *info* method for group and channel numbers

If the *raster* keyword argument is not *None* the output is interpolated accordingly.

Parameters

name [string] name of channel

group [int] 0-based group index

index [int] 0-based channel index

raster [float] time raster in seconds

samples_only [bool] if *True* return only the channel samples as numpy array; if *False* return a *Signal* object

data [bytes] prevent redundant data read by providing the raw data group samples

raw [bool] return channel samples without applying the conversion rule; default *False*

ignore_invalidation_bits [bool] only defined to have the same API with the MDF v4

record_offset [int] if *data=None* use this to select the record offset from which the group data should be loaded

Returns

res [(numpy.array, None) | *Signal*] returns *Signal* if *samples_only=False* (default option), otherwise returns a (numpy.array, None) tuple (for compatibility with MDF v4 class).

The *Signal* samples are

- numpy recarray for channels that have CDBLOCK or BYTEARRAY type channels
- numpy array for all the rest

Raises

MdfException :

- if the channel name is not found
- if the group index is out of range
- if the channel index is out of range

Examples

```
>>> from asammdf import MDF, Signal
>>> import numpy as np
>>> t = np.arange(5)
>>> s = np.ones(5)
>>> mdf = MDF(version='3.30')
>>> for i in range(4):
...     sigs = [Signal(s*(i*10+j), t, name='Sig') for j in range(1, 4)]
...     mdf.append(sigs)
...
>>> # first group and channel index of the specified channel name
...
>>> mdf.get('Sig')
UserWarning: Multiple occurrences for channel "Sig". Using first occurrence.
↳from data group 4. Provide both "group" and "index" arguments to select.
↳another data group
<Signal Sig:
  samples=[ 1.  1.  1.  1.  1.]
  timestamps=[0 1 2 3 4]
  unit=""
  info=None
  comment="">
>>> # first channel index in the specified group
...
>>> mdf.get('Sig', 1)
<Signal Sig:
```

(continues on next page)

(continued from previous page)

```

        samples=[ 11.  11.  11.  11.  11.]
        timestamps=[0 1 2 3 4]
        unit=""
        info=None
        comment="">
>>> # channel named Sig from group 1 channel index 2
...
>>> mdf.get('Sig', 1, 2)
<Signal Sig:
  samples=[ 12.  12.  12.  12.  12.]
  timestamps=[0 1 2 3 4]
  unit=""
  info=None
  comment="">
>>> # channel index 1 or group 2
...
>>> mdf.get(None, 2, 1)
<Signal Sig:
  samples=[ 21.  21.  21.  21.  21.]
  timestamps=[0 1 2 3 4]
  unit=""
  info=None
  comment="">
>>> mdf.get(group=2, index=1)
<Signal Sig:
  samples=[ 21.  21.  21.  21.  21.]
  timestamps=[0 1 2 3 4]
  unit=""
  info=None
  comment="">

```

get_channel_comment (*name=None, group=None, index=None*)

Gets channel comment. Channel can be specified in two ways:

- using the first positional argument *name*
 - if there are multiple occurrences for this channel then the *group* and *index* arguments can be used to select a specific group.
 - if there are multiple occurrences for this channel and either the *group* or *index* arguments is *None* then a warning is issued
- using the group number (keyword argument *group*) and the channel number (keyword argument *index*). Use *info* method for group and channel numbers

If the *raster* keyword argument is not *None* the output is interpolated accordingly.

Parameters

name [string] name of channel
group [int] 0-based group index
index [int] 0-based channel index

Returns

comment [str] found channel comment

get_channel_name (*group, index*)

Gets channel name.

Parameters

group [int] 0-based group index

index [int] 0-based channel index

Returns

name [str] found channel name

get_channel_unit (*name=None, group=None, index=None*)

Gets channel unit.

Channel can be specified in two ways:

- using the first positional argument *name*
 - if there are multiple occurrences for this channel then the *group* and *index* arguments can be used to select a specific group.
 - if there are multiple occurrences for this channel and either the *group* or *index* arguments is None then a warning is issued
- using the group number (keyword argument *group*) and the channel number (keyword argument *index*). Use *info* method for group and channel numbers

If the *raster* keyword argument is not *None* the output is interpolated accordingly.

Parameters

name [string] name of channel

group [int] 0-based group index

index [int] 0-based channel index

Returns

unit [str] found channel unit

get_master (*index, data=None, raster=None, record_offset=0, record_count=None, one_piece=False*)

returns master channel samples for given group

Parameters

index [int] group index

data [(bytes, int)] (data block raw bytes, fragment offset); default None

raster [float] raster to be used for interpolation; default None

Deprecated since version 5.13.0.

record_offset [int] if *data=None* use this to select the record offset from which the group data should be loaded

Returns

t [numpy.array] master channel samples

info ()

get MDF information as a dict

Examples

```
>>> mdf = MDF3('test.mdf')
>>> mdf.info()
```

iter_get_triggers()
generator that yields triggers

Returns

trigger_info [dict] trigger information with the following keys:

- **comment** : trigger comment
- **time** : trigger time
- **pre_time** : trigger pre time
- **post_time** : trigger post time
- **index** : trigger index
- **group** : data group index of trigger

save (*dst*, *overwrite=False*, *compression=0*)

Save MDF to *dst*. If *overwrite* is *True* then the destination file is overwritten, otherwise the file name is appended with '*<cntr>*', where '*<cntr>*' is the first counter that produces a new file name (that does not already exist in the filesystem).

Parameters

- dst** [str | pathlib.Path] destination file name
- overwrite** [bool] overwrite flag, default *False*
- compression** [int] does nothing for mdf version3; introduced here to share the same API as mdf version 4 files

Returns

output_file [str] output file name

2.2.1 MDF version 2 & 3 blocks

The following classes implement different MDF version3 blocks.

2.2.1.1 Channel Class

class `asammdf.blocks.v2_v3_blocks.Channel` (***kwargs*)
CNBLOCK class

If the *load_metadata* keyword argument is not provided or is *False*, then the conversion, source and display name information is not processed.

CNBLOCK fields

- **id** - bytes : block ID; always b'CN'
- **block_len** - int : block bytes size
- **next_ch_addr** - int : next CNBLOCK address
- **conversion_addr** - int : address of channel conversion block

- `source_addr` - int : address of channel source block
- `component_addr` - int : address of dependency block (CDBLOCK) of this channel
- `comment_addr` - int : address of TXBLOCK that contains the channel comment
- `channel_type` - int : integer code for channel type
- `short_name` - bytes : short signal name
- `description` - bytes : signal description
- `start_offset` - int : start offset in bits to determine the first bit of the signal in the data record
- `bit_count` - int : channel bit count
- `data_type` - int : integer code for channel data type
- `range_flag` - int : value range valid flag
- `min_raw_value` - float : min raw value of all samples
- `max_raw_value` - float : max raw value of all samples
- `sampling_rate` - float : sampling rate in 's' for a virtual time channel
- `long_name_addr` - int : address of TXBLOCK that contains the channel's name
- `display_name_addr` - int : address of TXBLOCK that contains the channel's display name
- `additional_byte_offset` - int : additional Byte offset of the channel in the data recor

Other attributes

- `address` - int : block address inside mdx file
- `comment` - str : channel comment
- `conversion` - ChannelConversion : channel conversion; *None* if the channel has no conversion
- `display_name` - str : channel display name
- `name` - str : full channel name
- `source` - SourceInformation : channel source information; *None* if the channel has no source information

Parameters

address [int] block address; to be used for objects created from file

stream [handle] file handle; to be used for objects created from file

load_metadata [bool] option to load conversion, source and display_name; default *True*

for dynamically created objects : see the key-value pairs

Examples

```
>>> with open('test.mdf', 'rb') as mdx:
...     ch1 = Channel(stream=mdx, address=0xBA52)
>>> ch2 = Channel()
>>> ch1.name
'VehicleSpeed'
>>> ch1['id']
b'CN'
```

2.2.1.2 ChannelConversion Class

class `asammdf.blocks.v2_v3_blocks.ChannelConversion` (**kwargs)
CCBLOCK class

ChannelConversion has the following common fields

- `id` - bytes : block ID; always b'CC'
- `block_len` - int : block bytes size
- `range_flag` - int : value range valid flag
- `min_phy_value` - float : min raw value of all samples
- `max_phy_value` - float : max raw value of all samples
- `unit` - bytes : physical unit
- `conversion_type` - int : integer code for conversion type
- `ref_param_nr` - int : number of referenced parameters

ChannelConversion has the following specific fields

- linear conversion
 - `a` - float : factor
 - `b` - float : offset
 - `CANapeHiddenExtra` - bytes : sometimes CANape appends extra information; not compliant with MDF specs
- algebraic conversion
 - `formula` - bytes : equation as string
- polynomial or rational conversion
 - `P1` to `P6` - float : parameters
- exponential or logarithmic conversion
 - `P1` to `P7` - float : parameters
- tabular with or without interpolation (grouped by index)
 - `raw_<N>` - int : N-th raw value (X axis)
 - `phys_<N>` - float : N-th physical value (Y axis)
- text table conversion
 - `param_val_<N>` - int : N-th raw value (X axis)
 - `text_<N>` - N-th text physical value (Y axis)
- text range table conversion
 - `default_lower` - float : default lower raw value
 - `default_upper` - float : default upper raw value
 - `default_addr` - int : address of default text physical value
 - `lower_<N>` - float : N-th lower raw value
 - `upper_<N>` - float : N-th upper raw value

- `text_<N>` - int : address of N-th text physical value

Other attributes

- `address` - int : block address inside mdf file
- `formula` - str : formula string in case of algebraic conversion
- `referenced_blocks` - list : list of CCBLOCK/TXBLOCK referenced by the conversion
- `unit` - str : physical unit

Parameters

address [int] block address inside mdf file

raw_bytes [bytes] complete block read from disk

stream [file handle] mdf file handle

for dynamically created objects : see the key-value pairs

Examples

```
>>> with open('test.mdf', 'rb') as mdf:
...     cc1 = ChannelConversion(stream=mdf, address=0xBA52)
>>> cc2 = ChannelConversion(conversion_type=0)
>>> cc1['b'], cc1['a']
0, 100.0
```

2.2.1.3 ChannelDependency Class

class `asammdf.blocks.v2_v3_blocks.ChannelDependency` (**kwargs)
CDBLOCK class

CDBLOCK fields

- `id` - bytes : block ID; always b'CD'
- `block_len` - int : block bytes size
- `dependency_type` - int : integer code for dependency type
- `sd_nr` - int : total number of signals dependencies
- `dq_<N>` - address of data group block (DGBLOCK) of N-th signal dependency
- `dq_<N>` - address of channel group block (CGBLOCK) of N-th signal dependency
- `dq_<N>` - address of channel block (CNBLOCK) of N-th signal dependency
- `dim_<K>` - int : Optional size of dimension *K* for N-dimensional dependency

Other attributes * `address` - int : block address inside mdf file * `referenced_channels` - list : list of (group index, channel index) pairs

Parameters

stream [file handle] mdf file handle

address [int] block address inside mdf file

for dynamically created objects : see the key-value pairs

2.2.1.4 ChannelExtension Class

class `asammdf.blocks.v2_v3_blocks.ChannelExtension` (***kwargs*)
CEBLOCK class

CEBLOCK has the following common fields

- `id` - bytes : block ID; always b'CE'
- `block_len` - int : block bytes size
- `type` - int : extension type identifier

CEBLOCK has the following specific fields

- for DIM block
 - `module_nr` - int: module number
 - `module_address` - int : module address
 - `description` - bytes : module description
 - `ECU_identification` - bytes : identification of ECU
 - `reserved0` - bytes : reserved bytes
- for Vector CAN block
 - `CAN_id` - int : CAN message ID
 - `CAN_ch_index` - int : index of CAN channel
 - `message_name` - bytes : message name
 - `sender_name` - bytes : sender name
 - `reserved0` - bytes : reserved bytes

Other attributes

- `address` - int : block address inside mdf file
- `comment` - str : extension comment
- `name` - str : extension name
- `path` - str : extension path

Parameters

stream [file handle] mdf file handle

address [int] block address inside mdf file

for dynamically created objects : see the key-value pairs

2.2.1.5 ChannelGroup Class

class `asammdf.blocks.v2_v3_blocks.ChannelGroup` (***kwargs*)
CGBLOCK class

CGBLOCK fields

- `id` - bytes : block ID; always b'CG'
- `block_len` - int : block bytes size

- `next_cg_addr` - int : next CGBLOCK address
- `first_ch_addr` - int : address of first channel block (CNBLOCK)
- `comment_addr` - int : address of TXBLOCK that contains the channel group comment
- `record_id` - int : record ID used as identifier for a record if the DGBLOCK defines a number of record IDs > 0 (unsorted group)
- `ch_nr` - int : number of channels
- `samples_byte_nr` - int : size of data record in bytes without record ID
- `cycles_nr` - int : number of cycles (records) of this type in the data block
- `sample_reduction_addr` - int : addresss to first sample reduction block

Other attributes

- `address` - int : block address inside mdf file
- `comment` - str : channel group comment

Parameters

stream [file handle] mdf file handle

address [int] block address inside mdf file

for dynamically created objects : see the key-value pairs

Examples

```
>>> with open('test.mdf', 'rb') as mdf:
...     cg1 = ChannelGroup(stream=mdf, address=0xBA52)
>>> cg2 = ChannelGroup(sample_bytes_nr=32)
>>> hex(cg1.address)
0xBA52
>>> cg1['id']
b'CG'
```

2.2.1.6 DataGroup Class

class `asammdf.blocks.v2_v3_blocks.DataGroup` (**kwargs)
DGBLOCK class

DGBLOCK fields

- `id` - bytes : block ID; always b'DG'
- `block_len` - int : block bytes size
- `next_dg_addr` - int : next DGBLOCK address
- `first_cg_addr` - int : address of first channel group block (CGBLOCK)
- `trigger_addr` - int : address of trigger block (TRBLOCK)
- `data_block_addr` - addrfss of data block
- `cg_nr` - int : number of channel groups
- `record_id_len` - int : number of record IDs in the data block

- `reserved0` - bytes : reserved bytes

Other attributes

- `address` - int : block address inside mdf file

Parameters

stream [file handle] mdf file handle

address [int] block address inside mdf file

for dynamically created objects : see the key-value pairs

2.2.1.7 FileIdentificationBlock Class

class `asammdf.blocks.v2_v3_blocks.FileIdentificationBlock` (**kwargs)

IDBLOCK class

IDBLOCK fields

- `file_identification` - bytes : file identifier
- `version_str` - bytes : format identifier
- `program_identification` - bytes : creator program identifier
- `byte_order` - int : integer code for byte order (endiannes)
- `float_format` - int : integer code for floating-point format
- `mdf_version` - int : version number of MDF format
- `code_page` - int : unicode code page number
- `reserved0` - bytes : reserved bytes
- `reserved1` - bytes : reserved bytes
- `unfinalized_standard_flags` - int : standard flags for unfinalized MDF
- `unfinalized_custom_flags` - int : custom flags for unfinalized MDF

Other attributes

- `address` - int : block address inside mdf file; should be 0 always

Parameters

stream [file handle] mdf file handle

version [int] mdf version in case of new file (dynamically created)

2.2.1.8 HeaderBlock Class

class `asammdf.blocks.v2_v3_blocks.HeaderBlock` (**kwargs)

HDBLOCK class

HDBLOCK fields

- `id` - bytes : block ID; always b'HD'
- `block_len` - int : block bytes size
- `first_dg_addr` - int : address of first data group block (DGBLOCK)

- `comment_addr` - int : address of TXBLOCK taht contains the measurement file comment
- `program_addr` - int : address of program block (PRBLOCK)
- `dg_nr` - int : number of data groups
- `date` - bytes : date at which the recording was started in “DD:MM:YYYY” format
- `time` - bytes : time at which the recording was started in “HH:MM:SS” format
- `author_field` - bytes : author name
- `organization_field`` - bytes : organization name
- `project_field`` - bytes : project name
- `subject_field`` - bytes : subject

Since version 3.2 the following extra keys were added

- `abs_time` - int : time stamp at which recording was started in nanoseconds.
- `tz_offset` - int : UTC time offset in hours (= GMT time zone)
- `time_quality` - int : time quality class
- `timer_identification` - bytes : timer identification (time source)

Other attributes

- `address` - int : block address inside mdm file; should be 64 always
- `comment` - int : file comment
- `program` - ProgramBlock : program block
- `author` - str : measurement author
- `department` - str : author department
- `project` - str : working project
- `subject` - str : measurement subject

Parameters

stream [file handle] mdm file handle

version [int] mdm version in case of new file (dynamically created)

2.2.1.9 ProgramBlock Class

class `asammdf.blocks.v2_v3_blocks.ProgramBlock` (***kwargs*)
PRBLOCK class

PRBLOCK fields

- `id` - bytes : block ID; always b'PR'
- `block_len` - int : block bytes size
- `data` - bytes : creator program free format data

Other attributes * `address` - int : block address inside mdm file

Parameters

stream [file handle] mdm file handle

address [int] block address inside mdf file

2.2.1.10 TextBlock Class

class asammdf.blocks.v2_v3_blocks.**TextBlock** (**kwargs)
TXBLOCK class

TXBLOCK fields

- **id** - bytes : block ID; always b'TX'
- **block_len** - int : block bytes size
- **text** - bytes : text content

Other attributes

- **address** - int : block address inside mdf file

Parameters

stream [file handle] mdf file handle

address [int] block address inside mdf file

text [bytes | str] bytes or str for creating a new TextBlock

Examples

```
>>> tx1 = TextBlock(text='VehicleSpeed')
>>> tx1.text_str
'VehicleSpeed'
>>> tx1['text']
b'VehicleSpeed'
```

2.2.1.11 TriggerBlock Class

class asammdf.blocks.v2_v3_blocks.**TriggerBlock** (**kwargs)
TRBLOCK class

TRBLOCK fields

- **id** - bytes : block ID; always b'TR'
- **block_len** - int : block bytes size
- **text_addr** - int : address of TXBLOCK that contains the trigger comment text
- **trigger_events_nr** - int : number of trigger events
- **trigger_<N>_time** - float : trigger time [s] of trigger's N-th event
- **trigger_<N>_pretime** - float : pre trigger time [s] of trigger's N-th event
- **trigger_<N>_posttime** - float : post trigger time [s] of trigger's N-th event

Other attributes

- **address** - int : block address inside mdf file
- **comment** - str : trigger comment

Parameters

stream [file handle] mdf file handle
address [int] block address inside mdf file

2.3 MDF4

class `asammdf.blocks.mdf_v4.MDF4` (*name=None*, *version='4.10'*, *channels=()*, ***kwargs*)

The *header* attribute is a *HeaderBlock*.

The *groups* attribute is a list of dicts, each one with the following keys:

- *data_group* - *DataGroup* object
- *channel_group* - *ChannelGroup* object
- *channels* - list of *Channel* objects with the same order as found in the mdf file
- *channel_dependencies* - list of *ChannelArrayBlock* in case of channel arrays; list of *Channel* objects in case of structure channel composition
- *data_block* - address of data block
- *data_location* - integer code for data location (original file, temporary file or memory)
- *data_block_addr* - list of raw samples starting addresses
- *data_block_type* - list of codes for data block type
- *data_block_size* - list of raw samples block size
- *sorted* - sorted indicator flag
- *record_size* - dict that maps record ID's to record sizes in bytes (including invalidation bytes)
- *param* - row size used for tranposition, in case of tranposed zipped blockss

Parameters

name [string] mdf file name (if provided it must be a real file name) or file-like object

version [string] mdf file version ('4.00', '4.10', '4.11', '4.20'); default '4.10'

kwargs :

callback [function] keyword only argument: function to call to update the progress; the function must accept two arguments (the current progress and maximum progress value)

use_display_names [bool] keyword only argument: for MDF4 files parse the XML channel comment to search for the display name; XML parsing is quite expensive so setting this to *False* can decrease the loading times very much; default *False*

remove_source_from_channel_names (**True**) [bool]

copy_on_get (**True**) [bool] copy channel values (np.array) to avoid high memory usage

compact_vlsd (**False**) [bool] use slower method to save the exact sample size for VLSD channels

column_storage (**True**) [bool] use column storage for MDF version >= 4.20

encryption_key [bytes] use this key to decode encrypted attachments

Attributes

attachments [list] list of file attachments

channels_db [dict] used for fast channel access by name; for each name key the value is a list of (group index, channel index) tuples

events [list] list event blocks

file_comment [TextBlock] file comment TextBlock

file_history [list] list of (FileHistory, TextBlock) pairs

groups [list] list of data group dicts

header [HeaderBlock] mdf file header

identification [FileIdentificationBlock] mdf file start block

last_call_info [dict | None] a dict to hold information about the last called method.

New in version 5.12.0.

masters_db [dict]

used for fast master channel access; for each group index key the value is the master channel index

name [string] mdf file name

version [str] mdf version

append (*signals*, *acq_name=None*, *acq_source=None*, *comment='Python'*, *common_timebase=False*, *units=None*)
Appends a new data group.

For channel dependencies type Signals, the *samples* attribute must be a numpy.recarray

Parameters

signals [list | Signal | pandas.DataFrame] list of *Signal* objects, or a single *Signal* object, or a pandas *DataFrame* object. All bytes columns in the pandas *DataFrame* must be *utf-8* encoded

acq_name [str] channel group acquisition name

acq_source [Source] channel group acquisition source

comment [str] channel group comment; default 'Python'

common_timebase [bool] flag to hint that the signals have the same timebase. Only set this if you know for sure that all appended channels share the same time base

units [dict] will contain the signal units mapped to the signal names when appending a pandas DataFrame

Examples

```
>>> # case 1 conversion type None
>>> s1 = np.array([1, 2, 3, 4, 5])
>>> s2 = np.array([-1, -2, -3, -4, -5])
>>> s3 = np.array([0.1, 0.04, 0.09, 0.16, 0.25])
>>> t = np.array([0.001, 0.002, 0.003, 0.004, 0.005])
>>> names = ['Positive', 'Negative', 'Float']
>>> units = ['+', '-', '.f']
>>> info = {}
```

(continues on next page)

(continued from previous page)

```

>>> s1 = Signal(samples=s1, timestamps=t, unit='+', name='Positive')
>>> s2 = Signal(samples=s2, timestamps=t, unit='-', name='Negative')
>>> s3 = Signal(samples=s3, timestamps=t, unit='flts', name='Floats')
>>> mdf = MDF4('new.mdf')
>>> mdf.append([s1, s2, s3], comment='created by asammdf v4.0.0')
>>> # case 2: VTAB conversions from channels inside another file
>>> mdf1 = MDF4('in.mf4')
>>> ch1 = mdf1.get("Channel1_VTAB")
>>> ch2 = mdf1.get("Channel2_VTABR")
>>> sigs = [ch1, ch2]
>>> mdf2 = MDF4('out.mf4')
>>> mdf2.append(sigs, comment='created by asammdf v4.0.0')
>>> mdf2.append(ch1, comment='just a single channel')
>>> df = pd.DataFrame.from_dict({'s1': np.array([1, 2, 3, 4, 5]), 's2': np.
    ↪array([-1, -2, -3, -4, -5])})
>>> units = {'s1': 'V', 's2': 'A'}
>>> mdf2.append(df, units=units)

```

attach (*data*, *file_name=None*, *hash_sum=None*, *comment=None*, *compression=True*,
mime='application/octet-stream', *embedded=True*, *encryption_function=None*)
 attach embedded attachment as application/octet-stream.

Parameters

data [bytes] data to be attached

file_name [str] string file name

hash_sum [bytes] md5 of the data

comment [str] attachment comment

compression [bool] use compression for embedded attachment data

mime [str] mime type string

embedded [bool] attachment is embedded in the file

encryption_function [bool, default None] function used to encrypt the data. The function should only take a single bytes object as argument and return the encrypted bytes object. This is only valid for embedded attachments

New in version 6.2.0.

Returns

index [int] new attachment index

close()

if the MDF was created with *memory=False* and new channels have been appended, then this must be called just before the object is not used anymore to clean-up the temporary file

configure (*, *from_other=None*, *read_fragment_size=None*, *write_fragment_size=None*,
use_display_names=None, *single_bit_uint_as_bool=None*, *integer_interpolation=None*,
copy_on_get=None, *float_interpolation=None*, *raise_on_multiple_occurrences=None*)
 configure MDF parameters.

The default values for the options are the following: * *read_fragment_size* = 0 * *write_fragment_size* = 4MB * *use_display_names* = False * *single_bit_uint_as_bool* = False * *integer_interpolation* = 0 (ffill - use previous sample) * *float_interpolation* = 1 (linear interpolation) * *copy_on_get* = False * *raise_on_multiple_occurrences* = True

Parameters

read_fragment_size [int] size hint of split data blocks, default 8MB; if the initial size is smaller, then no data list is used. The actual split size depends on the data groups' records size

write_fragment_size [int] size hint of split data blocks, default 4MB; if the initial size is smaller, then no data list is used. The actual split size depends on the data groups' records size. Maximum size is 4MB to ensure compatibility with CANape

use_display_names [bool] search for display name in the Channel XML comment

single_bit_uint_as_bool [bool] return single bit channels are np.bool arrays

integer_interpolation [int] interpolation mode for integer channels:

- 0 - repeat previous sample
- 1 - use linear interpolation
- 2 - hybrid interpolation: channels with integer data type (raw values) that have a conversion that outputs float values will use linear interpolation, otherwise the previous sample is used

Changed in version 6.2.0: added hybrid mode interpolation

copy_on_get [bool] copy arrays in the get method

float_interpolation [int] interpolation mode for float channels:

- 0 - repeat previous sample
- 1 - use linear interpolation

New in version 6.2.0.

raise_on_multiple_occurrences [bool] raise exception when there are multiple channel occurrences in the file and the *get* call is ambiguous; default True

New in version 6.2.0.

from_other [MDF] copy configuration options from other MDF

New in version 6.2.0.

extend (*index*, *signals*)

Extend a group with new samples. *signals* contains (values, invalidation_bits) pairs for each extended signal. The first pair is the master channel's pair, and the next pairs must respect the same order in which the signals were appended. The samples must have raw or physical values according to the *Signals* used for the initial append.

Parameters

index [int] group index

signals [list] list on (numpy.ndarray, numpy.ndarray) objects

Examples

```
>>> # case 1 conversion type None
>>> s1 = np.array([1, 2, 3, 4, 5])
>>> s2 = np.array([-1, -2, -3, -4, -5])
>>> s3 = np.array([0.1, 0.04, 0.09, 0.16, 0.25])
```

(continues on next page)

(continued from previous page)

```

>>> t = np.array([0.001, 0.002, 0.003, 0.004, 0.005])
>>> names = ['Positive', 'Negative', 'Float']
>>> units = ['+', '-', '.f']
>>> s1 = Signal(samples=s1, timestamps=t, unit='+', name='Positive')
>>> s2 = Signal(samples=s2, timestamps=t, unit='-', name='Negative')
>>> s3 = Signal(samples=s3, timestamps=t, unit='flts', name='Floats')
>>> mdf = MDF4('new.mdf')
>>> mdf.append([s1, s2, s3], comment='created by asammdf v1.1.0')
>>> t = np.array([0.006, 0.007, 0.008, 0.009, 0.010])
>>> # extend without invalidation bits
>>> mdf2.extend(0, [(t, None), (s1, None), (s2, None), (s3, None)])
>>> # some invalidiation btis
>>> s1_inv = np.array([0,0,0,1,1], dtype=np.bool)
>>> mdf2.extend(0, [(t, None), (s1.samples, None), (s2.samples, None), (s3.
→samples, None)])

```

extract_attachment

extract attachment data by index. If it is an embedded attachment, then this method creates the new file according to the attachment file name information

Parameters

index [int] attachment index; default *None*

decryption_function [bool, default *None*] function used to decrypt the data. The function should only take a single bytes object as argument and return the decrypted bytes object. This is only valid for embedded attachments

New in version 6.2.0.

Returns

data [(bytes, pathlib.Path)] tuple of attachment data and path

get (*name=None, group=None, index=None, raster=None, samples_only=False, data=None, raw=False, ignore_invalidation_bits=False, record_offset=0, record_count=None*)
Gets channel samples. The raw data group samples are not loaded to memory so it is advised to use *filter* or *select* instead of performing several *get* calls.

Channel can be specified in two ways:

- using the first positional argument *name*
 - if there are multiple occurrences for this channel then the *group* and *index* arguments can be used to select a specific group.
 - if there are multiple occurrences for this channel and either the *group* or *index* arguments is *None* then a warning is issued
- using the group number (keyword argument *group*) and the channel number (keyword argument *index*). Use *info* method for group and channel numbers

If the *raster* keyword argument is not *None* the output is interpolated accordingly

Parameters

name [string] name of channel

group [int] 0-based group index

index [int] 0-based channel index

raster [float] time raster in seconds

samples_only [bool]

if *True* return only the channel samples as numpy array; if *False* return a *Signal* object

data [bytes] prevent redundant data read by providing the raw data group samples

raw [bool] return channel samples without applying the conversion rule; default *False*

ignore_invalidation_bits [bool] option to ignore invalidation bits

record_offset [int] if *data=None* use this to select the record offset from which the group data should be loaded

record_count [int] number of records to read; default *None* and in this case all available records are used

Returns

res [(numpy.array, numpy.array) | *Signal*] returns *Signal* if *samples_only=False* (default option), otherwise returns a (numpy.array, numpy.array) tuple of samples and invalidation bits. If invalidation bits are not used or if *ignore_invalidation_bits* if *False*, then the second item will be *None*.

The *Signal* samples are:

- numpy recarray for channels that have composition/channel array address or for channel of type CANOPENDATE, CANOPENTIME
- numpy array for all the rest

Raises

MdfException :

- if the channel name is not found
- if the group index is out of range
- if the channel index is out of range

Examples

```
>>> from asammdf import MDF, Signal
>>> import numpy as np
>>> t = np.arange(5)
>>> s = np.ones(5)
>>> mdf = MDF(version='4.10')
>>> for i in range(4):
...     sigs = [Signal(s*(i*10+j), t, name='Sig') for j in range(1, 4)]
...     mdf.append(sigs)
...
>>> # first group and channel index of the specified channel name
...
>>> mdf.get('Sig')
UserWarning: Multiple occurrences for channel "Sig". Using first occurrence_
↳from data group 4. Provide both "group" and "index" arguments to select_
↳another data group
<Signal Sig:
  samples=[ 1.  1.  1.  1.  1.]
  timestamps=[0 1 2 3 4]
```

(continues on next page)

(continued from previous page)

```

        unit=""
        info=None
        comment="">
>>> # first channel index in the specified group
...
>>> mdf.get('Sig', 1)
<Signal Sig:
  samples=[ 11.  11.  11.  11.  11.]
  timestamps=[0 1 2 3 4]
  unit=""
  info=None
  comment="">
>>> # channel named Sig from group 1 channel index 2
...
>>> mdf.get('Sig', 1, 2)
<Signal Sig:
  samples=[ 12.  12.  12.  12.  12.]
  timestamps=[0 1 2 3 4]
  unit=""
  info=None
  comment="">
>>> # channel index 1 or group 2
...
>>> mdf.get(None, 2, 1)
<Signal Sig:
  samples=[ 21.  21.  21.  21.  21.]
  timestamps=[0 1 2 3 4]
  unit=""
  info=None
  comment="">
>>> mdf.get(group=2, index=1)
<Signal Sig:
  samples=[ 21.  21.  21.  21.  21.]
  timestamps=[0 1 2 3 4]
  unit=""
  info=None
  comment="">

```

get_bus_signal (*bus*, *name*, *database=None*, *ignore_invalidation_bits=False*, *data=None*, *raw=False*, *ignore_value2text_conversion=True*)

get a signal decoded from a raw bus logging. The currently supported buses are CAN and LIN (LDF databases are not supported, they need to be converted to DBC and feed to this function)

New in version 6.0.0.

Parameters

bus [str] “CAN” or “LIN”

name [str] signal name

database [str] path of external CAN/LIN database file (.dbc or .arxml) or canmatrix.CanMatrix; default *None*

Changed in version 6.0.0: *db* and *database* arguments were merged into this single argument

ignore_invalidation_bits [bool] option to ignore invalidation bits

raw [bool] return channel samples without applying the conversion rule; default *False*

ignore_value2text_conversion [bool] return channel samples without values that have a description in .dbc or .arxml file *True*

Returns

sig [Signal] Signal object with the physical values

get_can_signal (*name*, *database=None*, *ignore_invalidation_bits=False*, *data=None*, *raw=False*, *ignore_value2text_conversion=True*)

get CAN message signal. You can specify an external CAN database (*database* argument) or canmatrix database object that has already been loaded from a file (*db* argument).

The signal name can be specified in the following ways

- CAN<ID>.<MESSAGE_NAME>.<SIGNAL_NAME> - the *ID* value starts from 1 and must match the ID found in the measurement (the source CAN bus ID) Example: CAN1.Wheels.FL_WheelSpeed
- CAN<ID>.CAN_DataFrame_<MESSAGE_ID>.<SIGNAL_NAME> - the *ID* value starts from 1 and the *MESSAGE_ID* is the decimal message ID as found in the database. Example: CAN1.CAN_DataFrame_218.FL_WheelSpeed
- <MESSAGE_NAME>.<SIGNAL_NAME> - in this case the first occurrence of the message name and signal are returned (the same message could be found on muplit CAN buses; for example on CAN1 and CAN3) Example: Wheels.FL_WheelSpeed
- CAN_DataFrame_<MESSAGE_ID>.<SIGNAL_NAME> - in this case the first occurrence of the message name and signal are returned (the same message could be found on muplit CAN buses; for example on CAN1 and CAN3). Example: CAN_DataFrame_218.FL_WheelSpeed
- <SIGNAL_NAME> - in this case the first occurrence of the signal name is returned (the same signal anme could be found in multiple messages and on multiple CAN buses). Example: FL_WheelSpeed

Parameters

name [str] signal name

database [str] path of external CAN database file (.dbc or .arxml) or canmatrix.CanMatrix; default *None*

Changed in version 6.0.0: *db* and *database* arguments were merged into this single argument

ignore_invalidation_bits [bool] option to ignore invalidation bits

raw [bool] return channel samples without applying the conversion rule; default *False*

ignore_value2text_conversion [bool] return channel samples without values that have a description in .dbc or .arxml file *True*

Returns

sig [Signal] Signal object with the physical values

get_channel_comment (*name=None*, *group=None*, *index=None*)

Gets channel comment.

Channel can be specified in two ways:

- using the first positional argument *name*
 - if there are multiple occurrences for this channel then the *group* and *index* arguments can be used to select a specific group.

- if there are multiple occurrences for this channel and either the *group* or *index* arguments is *None* then a warning is issued
- using the group number (keyword argument *group*) and the channel number (keyword argument *index*). Use *info* method for group and channel numbers

If the *raster* keyword argument is not *None* the output is interpolated accordingly.

Parameters

name [string] name of channel
group [int] 0-based group index
index [int] 0-based channel index

Returns

comment [str] found channel comment

get_channel_name (*group*, *index*)

Gets channel name.

Parameters

group [int] 0-based group index
index [int] 0-based channel index

Returns

name [str] found channel name

get_channel_unit (*name=None*, *group=None*, *index=None*)

Gets channel unit.

Channel can be specified in two ways:

- using the first positional argument *name*
 - if there are multiple occurrences for this channel then the *group* and *index* arguments can be used to select a specific group.
 - if there are multiple occurrences for this channel and either the *group* or *index* arguments is *None* then a warning is issued
- using the group number (keyword argument *group*) and the channel number (keyword argument *index*). Use *info* method for group and channel numbers

If the *raster* keyword argument is not *None* the output is interpolated accordingly.

Parameters

name [string] name of channel
group [int] 0-based group index
index [int] 0-based channel index

Returns

unit [str] found channel unit

get_invalidation_bits (*group_index*, *channel*, *fragment*)

get invalidation indexes for the channel

Parameters

group_index [int] group index

channel [Channel] channel object

fragment [(bytes, int)] (fragment bytes, fragment offset)

Returns

invalidation_bits [iterable] iterable of valid channel indexes; if all are valid *None* is returned

get_lin_signal (*name*, *database=None*, *ignore_invalidation_bits=False*, *data=None*, *raw=False*, *ignore_value2text_conversion=True*)

get LIN message signal. You can specify an external LIN database (*database* argument) or canmatrix database object that has already been loaded from a file (*db* argument).

The signal name can be specified in the following ways

- LIN_Frame_<MESSAGE_ID>.<SIGNAL_NAME> - Example: LIN_Frame_218.FL_WheelSpeed
- <MESSAGE_NAME>.<SIGNAL_NAME> - Example: Wheels.FL_WheelSpeed
- <SIGNAL_NAME> - Example: FL_WheelSpeed

New in version 6.0.0.

Parameters

name [str] signal name

database [str] path of external LIN database file (.dbc, .arxml or .ldf) or canmatrix.CanMatrix; default *None*

ignore_invalidation_bits [bool] option to ignore invalidation bits

raw [bool] return channel samples without applying the conversion rule; default *False*

ignore_value2text_conversion [bool] return channel samples without values that have a description in .dbc, .arxml or .ldf file *True*

Returns

sig [Signal] Signal object with the physical values

get_master (*index*, *data=None*, *raster=None*, *record_offset=0*, *record_count=None*, *one_piece=False*)

returns master channel samples for given group

Parameters

index [int] group index

data [(bytes, int, int, bytes|None)] (data block raw bytes, fragment offset, count, invalidation bytes); default *None*

raster [float] raster to be used for interpolation; default *None*

Deprecated since version 5.13.0.

record_offset [int] if *data=None* use this to select the record offset from which the group data should be loaded

record_count [int] number of records to read; default *None* and in this case all available records are used

Returns

t [numpy.array] master channel samples

info()
get MDF information as a dict

Examples

```
>>> mdf = MDF4('test.mdf')
>>> mdf.info()
```

save (*dst*, *overwrite=False*, *compression=0*)

Save MDF to *dst*. If *overwrite* is *True* then the destination file is overwritten, otherwise the file name is appened with '*<cntr>*', were '*<cntr>*' is the first conter that produces a new file name (that does not already exist in the filesystem)

Parameters

dst [str] destination file name, Default ''

overwrite [bool] overwrite flag, default *False*

compression [int] use compressed data blocks, default 0; valid since version 4.10

- 0 - no compression
- 1 - deflate (slower, but produces smaller files)
- 2 - transposition + deflate (slowest, but produces the smallest files)

Returns

output_file [pathlib.Path] path to saved file

2.3.1 MDF version 4 blocks

The following classes implement different MDF version4 blocks.

2.3.1.1 AttachmentBlock Class

class asammdf.blocks.v4_blocks.**AttachmentBlock** (***kwargs*)

When adding new attachments only embedded attachments are allowed, with keyword argument *data* of type bytes

AttachmentBlock has the following attributes, that are also available as dict like key-value pairs

ATBLOCK fields

- **id** - bytes : block ID; always b'##AT'
- **reserved0** - int : reserved bytes
- **block_len** - int : block bytes size
- **links_nr** - int : number of links
- **next_at_addr** - int : next ATBLOCK address
- **file_name_addr** - int : address of TXBLOCK that contains the attachment file name
- **mime_addr** - int : address of TXBLOCK that contains the attachment mime type description
- **comment_addr** - int : address of TXBLOCK/MDBLOCK that contains the attachment comment
- **flags** - int : ATBLOCK flags

- `creator_index` - int : index of file history block
- `reserved1` - int : reserved bytes
- `md5_sum` - bytes : attachment file md5 sum
- `original_size` - int : original uncompress file size in bytes
- `embedded_size` - int : embedded compressed file size in bytes
- `embedded_data` - bytes : embedded attachment bytes

Other attributes

- `address` - int : attachment address
- `file_name` - str : attachment file name
- `mime` - str : mime type
- `comment` - str : attachment comment

Parameters

address [int] block address; to be used for objects created from file
stream [handle] file handle; to be used for objects created from file
for dynamically created objects : see the key-value pairs

extract ()
 extract attachment data

Returns

data [bytes]

2.3.1.2 Channel Class

class `asammdf.blocks.v4_blocks.Channel` (**kwargs)

If the *load_metadata* keyword argument is not provided or is False, then the conversion, source and display name information is not processed. Further more if the *parse_xml_comment* is not provided or is False, then the display name information from the channel comment is not processed (this is done to avoid expensive XML operations)

Channel has the following attributes, that are also available as dict like key-value pairs

CNBLOCK fields

- `id` - bytes : block ID; always b'##CN'
- `reserved0` - int : reserved bytes
- `block_len` - int : block bytes size
- `links_nr` - int : number of links
- `next_ch_addr` - int : next ATBLOCK address
- `component_addr` - int : address of first channel in case of structure channel composition, or ChannelArrayBlock in case of arrays file name
- `name_addr` - int : address of TXBLOCK that contains the channel name
- `source_addr` - int : address of channel source block

- `conversion_addr` - int : address of channel conversion block
- `data_block_addr` - int : address of signal data block for VLSD channels
- `unit_addr` - int : address of TXBLOCK that contains the channel unit
- `comment_addr` - int : address of TXBLOCK/MDBLOCK that contains the channel comment
- `attachment_<N>_addr` - int : address of N-th ATBLOCK referenced by the current channel; if no ATBLOCK is referenced there will be no such key-value pair
- `default_X_dg_addr` - int : address of DGBLOCK where the default X axis channel for the current channel is found; this key-value pair will not exist for channels that don't have a default X axis
- `default_X_cg_addr` - int : address of CGBLOCK where the default X axis channel for the current channel is found; this key-value pair will not exist for channels that don't have a default X axis
- `default_X_ch_addr` - int : address of default X axis channel for the current channel; this key-value pair will not exist for channels that don't have a default X axis
- `channel_type` - int : integer code for the channel type
- `sync_type` - int : integer code for the channel's sync type
- `data_type` - int : integer code for the channel's data type
- `bit_offset` - int : bit offset
- `byte_offset` - int : byte offset within the data record
- `bit_count` - int : channel bit count
- `flags` - int : CNBLOCK flags
- `pos_invalidation_bit` - int : invalidation bit position for the current channel if there are invalidation bytes in the data record
- `precision` - int : integer code for the precision
- `reserved1` - int : reserved bytes
- `min_raw_value` - int : min raw value of all samples
- `max_raw_value` - int : max raw value of all samples
- `lower_limit` - int : min physical value of all samples
- `upper_limit` - int : max physical value of all samples
- `lower_ext_limit` - int : min physical value of all samples
- `upper_ext_limit` - int : max physical value of all samples

Other attributes

- `address` - int : channel address
- `attachments` - list : list of referenced attachment blocks indexes; the index refers to the attachment block index
- `comment` - str : channel comment
- `conversion` - ChannelConversion : channel conversion; *None* if the channel has no conversion
- `display_name` - str : channel display name; this is extracted from the XML channel comment
- `name` - str : channel name
- `source` - SourceInformation : channel source information; *None* if the channel has no source information

- `unit` - str : channel unit

Parameters

address [int] block address; to be used for objects created from file

stream [handle] file handle; to be used for objects created from file

load_metadata [bool] option to load conversion, source and display_name; default *True*

parse_xml_comment [bool] option to parse XML channel comment to search for display name; default *True*

for dynamically created objects : see the key-value pairs

2.3.1.3 ChannelConversion Class

class `asammdf.blocks.v4_blocks.ChannelConversion (**kwargs)`

ChannelConversion has the following attributes, that are also available as dict like key-value pairs

CCBLOCK common fields

- `id` - bytes : block ID; always `b'##CG'`
- `reserved0` - int : reserved bytes
- `block_len` - int : block bytes size
- `links_nr` - int : number of links
- `name_addr` - int : address of TXBLOCK that contains the conversion name
- `unit_addr` - int : address of TXBLOCK that contains the conversion unit
- `comment_addr` - int : address of TXBLOCK/MDBLOCK that contains the conversion comment
- `inv_conv_addr` - int : address of invers conversion
- `conversion_type` - int : integer code for conversion type
- `precision` - int : integer code for precision
- `flags` - int : conversion block flags
- `ref_param_nr` - int : number fo referenced parameters (linked parameters)
- `val_param_nr` - int : number of value parameters
- `min_phy_value` - float : minimum physical channel value
- `max_phy_value` - float : maximum physical channel value

CCBLOCK specific fields

- linear conversion
 - `a` - float : factor
 - `b` - float : offset
- rational conversion
 - `P1` to `P6` - float : parameters
- algebraic conversion
 - `formula_addr` - address of TXBLOCK that contains the the algebraic conversion formula

- tabluar conversion with or without interpolation
 - raw_<N> - float : N-th raw value
 - phys_<N> - float : N-th physical value
- tabular range conversion
 - lower_<N> - float : N-th lower value
 - upper_<N> - float : N-th upper value
 - phys_<N> - float : N-th physical value
- tabular value to text conversion
 - val_<N> - float : N-th raw value
 - text_<N> - int : address of N-th TXBLOCK that contains the physical value
 - default - int : address of TXBLOCK that contains the default physical value
- tabular range to text conversion
 - lower_<N> - float : N-th lower value
 - upper_<N> - float : N-th upper value
 - text_<N> - int : address of N-th TXBLOCK that contains the physical value
 - default - int : address of TXBLOCK that contains the default physical value
- text to value conversion
 - val_<N> - float : N-th physical value
 - text_<N> - int : address of N-th TXBLOCK that contains the raw value
 - val_default - float : default physical value
- text tranfosrmation (translation) conversion
 - input_<N>_addr - int : address of N-th TXBLOCK that contains the raw value
 - output_<N>_addr - int : address of N-th TXBLOCK that contains the physical value
 - default_addr - int : address of TXBLOCK that contains the default physical value

Other attributes

- address - int : channel conversion address
- comment - str : channel conversion comment
- formula - str : algebraic conversion formula; default ''
- referenced_blocks - dict : dict of refenced blocks; can be TextBlock objects for value to text, and text to text conversions; for partial conversions the referenced blocks can be ChannelConversion obejct as well
- name - str : channel conversion name
- unit - str : channel conversion unit

2.3.1.4 ChannelGroup Class

class asammdf.blocks.v4_blocks.ChannelGroup (**kwargs)

ChannelGroup has the following attributes, that are also available as dict like key-value pairs

CGBLOCK fields

- `id - bytes` : block ID; always `b'##CG'`
- `reserved0 - int` : reserved bytes
- `block_len - int` : block bytes size
- `links_nr - int` : number of links
- `next_cg_addr - int` : next channel group address
- `first_ch_addr - int` : address of first channel of this channel group
- `acq_name_addr - int` : address of TextBlock that contains the channel group acquisition name
- `acq_source_addr - int` : address of SourceInformation that contains the channel group source
- `first_sample_reduction_addr - int` : address of first SRBLOCK; this is considered 0 since sample reduction is not yet supported
- `comment_addr - int` : address of TXBLOCK/MDBLOCK that contains the channel group comment
- `record_id - int` : record ID for the channel group
- `cycles_nr - int` : number of cycles for this channel group
- `flags - int` : channel group flags
- `path_separator - int` : ordinal for character used as path separator
- `reserved1 - int` : reserved bytes
- `samples_byte_nr - int` : number of bytes used for channels samples in the record for this channel group; this does not contain the invalidation bytes
- `invalidation_bytes_nr - int` : number of bytes used for invalidation bits by this channel group

Other attributes

- `acq_name - str` : acquisition name
- `acq_source - SourceInformation` : acquisition source information
- `address - int` : channel group address
- `comment - str` : channel group comment

2.3.1.5 DataGroup Class

class asammdf.blocks.v4_blocks.DataGroup (**kwargs)

DataGroup has the following attributes, that are also available as dict like key-value pairs

DGBLOCK fields

- `id - bytes` : block ID; always `b'##DG'`
- `reserved0 - int` : reserved bytes
- `block_len - int` : block bytes size
- `links_nr - int` : number of links

- `next_dg_addr` - int : address of next data group block
- `first_cg_addr` - int : address of first channel group for this data group
- `data_block_addr` - int : address of DTBLOCK, DZBLOCK, DLBLOCK or HLBLOCK that contains the raw samples for this data group
- `comment_addr` - int : address of TXBLOCK/MDBLOCK tha contains the data group comment
- `record_id_len` - int : size of record ID used in case of unsorted data groups; can be 1, 2, 4 or 8
- `reserved1` - int : reserved bytes

Other attributes

- `address` - int : dat group address
- `comment` - str : data group comment

2.3.1.6 DataList Class

class `asammdf.blocks.v4_blocks.DataList` (**kwargs)

DataList has the following attributes, that are also available as dict like key-value pairs

DLBLOCK common fields

- `id` - bytes : block ID; always b'##DL'
- `reserved0` - int : reserved bytes
- `block_len` - int : block bytes size
- `links_nr` - int : number of links
- `next_dl_addr` - int : address of next DLBLOCK
- `data_block_addr<N>` - int : address of N-th data block
- `flags` - int : data list flags
- `reserved1` - int : reserved bytes
- `data_block_nr` - int : number of data blocks referenced by this list

DLBLOCK specific fields

- for equall lenght blocks
 - `data_block_len` - int : equall uncompressed size in bytes for all referenced data blocks; last block can be smaller
- for variable lenght blocks
 - `offset_<N>` - int : byte offset of N-th data block

Other attributes

- `address` - int : data list address

2.3.1.7 DataBlock Class

class `asammdf.blocks.v4_blocks.DataBlock` (**kwargs)

Common implementation for DTBLOCK/RDBLOCK/SDBLOCK/DVBLOCK/DIBLOCK

DataBlock has the following attributes, that are also available as dict like key-value pairs

DTBLOCK fields

- `id` - bytes : block ID; `b'##DT'` for DTBLOCK, `b'##RD'` for RDBLOCK, `b'##SD'` for SDBLOCK, `b'##DV'` for DVBLOCK or `b'##DI'` for DIBLOCK
- `reserved0` - int : reserved bytes
- `block_len` - int : block bytes size
- `links_nr` - int : number of links
- `data` - bytes : raw samples

Other attributes

- `address` - int : data block address

Parameters

address [int] DTBLOCK/RDBLOCK/SDBLOCK/DVBLOCK/DIBLOCK address inside the file

stream [int] file handle

reduction [bool] sample reduction data block

2.3.1.8 FileIdentificationBlock Class

class `asammdf.blocks.v4_blocks.FileIdentificationBlock` (**kwargs)

FileIdentificationBlock has the following attributes, that are also available as dict like key-value pairs

IDBLOCK fields

- `file_identification` - bytes : file identifier
- `version_str` - bytes : format identifier
- `program_identification` - bytes : creator program identifier
- `reserved0` - bytes : reserved bytes
- `mdf_version` - int : version number of MDF format
- `reserved1` - bytes : reserved bytes
- `unfinalized_standard_flags` - int : standard flags for unfinalized MDF
- `unfinalized_custom_flags` - int : custom flags for unfinalized MDF

Other attributes

- `address` - int : should always be 0

2.3.1.9 HeaderBlock Class

class `asammdf.blocks.v4_blocks.HeaderBlock` (**kwargs)

HeaderBlock has the following attributes, that are also available as dict like key-value pairs

HDBLOCK fields

- `id` - bytes : block ID; always `b'##HD'`
- `reserved0` - int : reserved bytes
- `block_len` - int : block bytes size

- `links_nr` - int : number of links
- `first_dg_addr` - int : address of first DGBLOCK
- `file_history_addr` - int : address of first FHBLOCK
- `channel_tree_addr` - int : address of first CHBLOCK
- `first_attachment_addr` - int : address of first ATBLOCK
- `first_event_addr` - int : address of first EVBLOCK
- `comment_addr` - int : address of TXBLOCK/MDBLOCK that contains the file comment
- `abs_time` - int : time stamp at which recording was started in nanoseconds.
- `tz_offset` - int : UTC time offset in hours (= GMT time zone)
- `daylight_save_time` - int : daylight saving time
- `time_flags` - int : time flags
- `time_quality` - int : time quality flags
- `flags` - int : file flags
- `reserved1` - int : reserved bytes
- `start_angle` - int : angle value at measurement start
- `start_distance` - int : distance value at measurement start

Other attributes

- `address` - int : header address
- `comment` - str : file comment
- `author` - str : measurement author
- `department` - str : author's department
- `project` - str : working project
- `subject` - str : measurement subject

start_time

getter and setter the measurement start timestamp

Returns

timestamp [datetime.datetime] start timestamp

2.3.1.10 SourceInformation Class

class `asammdf.blocks.v4_blocks.SourceInformation` (**kwargs)

SourceInformation has the following attributes, that are also available as dict like key-value pairs

SIBLOCK fields

- `id` - bytes : block ID; always b'##SI'
- `reserved0` - int : reserved bytes
- `block_len` - int : block bytes size
- `links_nr` - int : number of links
- `name_addr` - int : address of TXBLOCK that contains the source name

- `path_addr` - int : address of TXBLOCK that contains the source path
- `comment_addr` - int : address of TXBLOCK/MDBLOCK tha contains the source comment
- `source_type` - int : integer code for source type
- `bus_type` - int : integer code for source bus type
- `flags` - int : source flags
- `reserved1` - bytes : reserved bytes

Other attributes

- `address` - int : source information address
- `comment` - str : source comment
- `name` - str : source name
- `path` - str : source path

2.3.1.11 FileHistory Class

class `asammdf.blocks.v4_blocks.FileHistory` (***kwargs*)

FileHistory has the following attributes, that are also available as dict like key-value pairs

FHBLOCK fields

- `id` - bytes : block ID; always `b'##FH'`
- `reserved0` - int : reserved bytes
- `block_len` - int : block bytes size
- `links_nr` - int : number of links
- `next_fh_addr` - int : address of next FHBLOCK
- `comment_addr` - int : address of TXBLOCK/MDBLOCK that contains the file history comment
- `abs_time` - int : time stamp at which the file modification happened
- `tz_offset` - int : UTC time offset in hours (= GMT time zone)
- `daylight_save_time` - int : daylight saving time
- `time_flags` - int : time flags
- `reserved1` - bytes : reserved bytes

Other attributes

- `address` - int : file history address
- `comment` - str : history comment

2.3.1.12 TextBlock Class

class `asammdf.blocks.v4_blocks.TextBlock` (***kwargs*)

common TXBLOCK and MDBLOCK class

TextBlock has the following attributes, that are also available as dict like key-value pairs

TXBLOCK fields

- `id` - bytes : block ID; b'##TX' for TXBLOCK and b'##MD' for MDBLOCK
- `reserved0` - int : reserved bytes
- `block_len` - int : block bytes size
- `links_nr` - int : number of links
- `text` - bytes : actual text content

Other attributes

- `address` - int : text block address

Parameters

address [int] block address

stream [handle] file handle

meta [bool] flag to set the block type to MDBLOCK for dynamically created objects; default *False*

text [bytes/str] text content for dynamically created objects

2.3.1.13 EventBlock Class

class `asammdf.blocks.v4_blocks.EventBlock` (**kwargs)

EventBlock has the following attributes, that are also available as dict like key-value pairs

EVBLOCK fields

- `id` - bytes : block ID; always b'##EV'
- `reserved0` - int : reserved bytes
- `block_len` - int : block bytes size
- `links_nr` - int : number of links
- `next_ev_addr` - int : address of next EVBLOCK
- `parent_ev_addr` - int : address of parent EVBLOCK
- `range_start_ev_addr` - int : address of EVBLOCK that is the start of the range for which this event is the end
- `name_addr` - int : address of TXBLOCK that contains the event name
- `comment_addr` - int : address of TXBLOCK/MDBLOCK that contains the event comment
- `scope_<N>_addr` - int : address of N-th block that represents a scope for this event (can be CGBLOCK, CHBLOCK, DGBLOCK)
- `attachmnt_<N>_addr` - int : address of N-th attachment referenced by this event
- `event_type` - int : integer code for event type
- `sync_type` - int : integer code for event sync type
- `range_type` - int : integer code for event range type
- `cause` - int : integer code for event cause
- `flags` - int : event flags
- `reserved1` - int : reserved bytes

- `scope_nr` - int : number of scopes referenced by this event
- `attachment_nr` - int : number of attachments referenced by this event
- `creator_index` - int : index of FHBLOCK
- `sync_base` - int : timestamp base value
- `sync_factor` - float : timestamp factor

Other attributes

- `address` - int : event block address
- `comment` - str : event comment
- `name` - str : event name
- `parent` - int : index of event block that is the parent for the current event
- `range_start` - int : index of event block that is the start of the range for which the current event is the end
- `scopes` - list : list of (group index, channel index) or channel group index that define the scope of the current event

2.4 Signal

```
class asammdf.signal.Signal(samples=None, timestamps=None, unit="", name="", conversion=None, comment="", raw=True, master_metadata=None, display_name="", attachment=(), source=None, bit_count=None, stream_sync=False, invalidation_bits=None, encoding=None, group_index=-1, channel_index=-1)
```

The *Signal* represents a channel described by it's samples and timestamps. It can perform arithmetic operations against other *Signal* or numeric types. The operations are computed in respect to the timestamps (time correct). The non-float signals are not interpolated, instead the last value relative to the current timestamp is used. *samples*, *timestamps* and *name* are mandatory arguments.

Parameters

- samples** [numpy.array | list | tuple] signal samples
- timestamps** [numpy.array | list | tuple] signal timestamps
- unit** [str] signal unit
- name** [str] signal name
- conversion** [dict | channel conversion block] dict that contains extra conversion information about the signal, default *None*
- comment** [str] signal comment, default ''
- raw** [bool] signal samples are raw values, with no physical conversion applied
- master_metadata** [list] master name and sync type
- display_name** [str] display name used by mdf version 3
- attachment** [bytes, name] channel attachment and name from MDF version 4
- source** [Source] source information named tuple
- bit_count** [int] bit count; useful for integer channels

stream_sync [bool] the channel is a synchronisation for the attachment stream (mdf v4 only)

invalidation_bits [numpy.array | None] channel invalidation bits, default *None*

encoding [str | None] encoding for string signals; default *None*

astype (*np_type*)

returns new *Signal* with samples of dtype *np_type*

Parameters

np_type [np.dtype] new numpy dtype

Returns

signal [Signal] new *Signal* with the samples of *np_type* dtype

copy ()

copy all attributes to a new *Signal*

cut (*start=None*, *stop=None*, *include_ends=True*, *interpolation_mode=None*, *integer_interpolation_mode=None*, *float_interpolation_mode=1*)

Cuts the signal according to the *start* and *stop* values, by using the insertion indexes in the signal's *time* axis.

Parameters

start [float] start timestamp for cutting

stop [float] stop timestamp for cutting

include_ends [bool] include the *start* and *stop* timestamps after cutting the signal. If *start* and *stop* are found in the original timestamps, then the new samples will be computed using interpolation. Default *True*

interpolation_mode [int] interpolation mode for integer signals; default 0. You should use the new *integer_interpolation_mode* argument since this will be deprecated in a later release

- 0 - repeat previous samples
- 1 - linear interpolation
- 2 - hybrid interpolation: channels with integer data type (raw values) that have a conversion that outputs float values will use linear interpolation, otherwise the previous sample is used

Changed in version 6.2.0: added hybrid mode interpolation

integer_interpolation_mode [int] interpolation mode for integer signals; default 0

- 0 - repeat previous samples
- 1 - linear interpolation
- 2 - hybrid interpolation: channels with integer data type (raw values) that have a conversion that outputs float values will use linear interpolation, otherwise the previous sample is used

New in version 6.2.0.

float_interpolation_mode [int] interpolation mode for float channels; default 1

- 0 - repeat previous sample
- 1 - use linear interpolation

New in version 6.2.0.

Returns

result [Signal] new *Signal* cut from the original

Examples

```
>>> new_sig = old_sig.cut(1.0, 10.5)
>>> new_sig.timestamps[0], new_sig.timestamps[-1]
0.98, 10.48
```

extend (*other*)

extend signal with samples from another signal

Parameters

other [Signal]

Returns

signal [Signal] new extended *Signal*

interp (*new_timestamps*, *interpolation_mode*=None, *integer_interpolation_mode*=None, *float_interpolation_mode*=1)

returns a new *Signal* interpolated using the *new_timestamps*

Parameters

new_timestamps [np.array] timestamps used for interpolation

interpolation_mode [int] interpolation mode for integer signals; default 0. You should use the new *integer_interpolation_mode* argument since this will be deprecated in a later release

- 0 - repeat previous samples
- 1 - linear interpolation
- 2 - hybrid interpolation: channels with integer data type (raw values) that have a conversion that outputs float values will use linear interpolation, otherwise the previous sample is used

Changed in version 6.2.0: added hybrid mode interpolation

integer_interpolation_mode [int] interpolation mode for integer signals; default 0

- 0 - repeat previous samples
- 1 - linear interpolation
- 2 - hybrid interpolation: channels with integer data type (raw values) that have a conversion that outputs float values will use linear interpolation, otherwise the previous sample is used

New in version 6.2.0.

float_interpolation_mode [int] interpolation mode for float channels; default 1

- 0 - repeat previous sample
- 1 - use linear interpolation

New in version 6.2.0.

Returns

signal [Signal] new interpolated *Signal*

physical ()

get the physical samples values

Returns

phys [Signal] new *Signal* with physical values

plot (*validate=True, index_only=False*)

plot Signal samples. Pyqtgraph is used if it is available; in this case see the GUI plot documentation to see the available commands

Parameters

validate (True): bool apply the invalidation bits

index_only (False) [bool] use index based X axis. This can be useful if the master (usually time based) is corrupted with NaN, inf or if it is not strictly increasing

validate (*copy=True*)

apply invalidation bits if they are available for this signal

Parameters

copy (True) [bool] return a copy of the result

New in version 5.12.0.

Initial read only mode for mdf version 4.10 files containing CAN/LIN bus logging is now implemented.

To handle this, the **canmatrix** package was added to the dependencies; you will need to install the latest code from the **canmatrix** library.

Let's take for example the following situation: the .dbc contains the definition for the CAN message called "VehicleStatus" with *ID=123*. This message contains the signal "EngineStatus". Logging was made from the CAN bus with *ID=1* (CAN1).

There multiple ways to address this channel in this situation:

1. short signal name as found in the .dbc file

```
mdf.get('EngineStatus')
```

2. dbc message name and short signal name, delimited by dot

```
mdf.get('VehicleStatus.EngineStatus')
```

3. CAN bus ID, dbc message name and short signal name, delimited by dot

```
mdf.get('CAN1.VehicleStatus.EngineStatus')
```

4. ASAM conformant message ID and short signal name, delimited by dot

```
mdf.get('CAN_DataFrame_123.EngineStatus')
```

5. CAN bus ID, ASAM conformant message ID and short signal name, delimited by dot

```
mdf.get('CAN1.CAN_DataFrame_123.EngineStatus')
```


4.1 Selective channel loading

Since `asammdf` 6.1.0 you can use the **channels** argument to perform a selective channel loading. Only the metadata of channels found in the selection iterable will be preserved after loading the file. This can yield a big speed improvement for loading the file, but also when performing operations with the MDF object (for example `select`, `get`, etc.).

```
required_channels = ["Speed", "Acceleration", "Force"]
mdf = MDF("input.mf4", channels=required_channels)
```

4.2 Data coupling

All the data returned by the MDF methods is decoupled from the raw data found in the original file. For example, if you modify the Signal returned by the `get` call the changes will not be seen in the raw data. A second `get` call of the same channel name will once again give you the data found in the original file.

4.3 Chunked data access

`asammdf` optimizes memory usage by processing samples in fragments. The read fragment size was tuned based on experimental measurements and should give a good compromise between execution time and memory usage.

You can further tune the read fragment size using the `configure` method, to favor execution speed (using larger fragment sizes) or memory usage (using lower fragment sizes).

4.4 Optimized methods

The *MDF* methods (`cut`, `filter`, `select`) are optimized and should be used instead of calling `get` for several channels.

Each *get* call will read all channel group raw samples from disk. If you need to extract multiple channels it is strongly advised to use the *select* method: for each channel group that contains channels submitted for selection, the raw samples will only be read once.

4.5 Faster file loading

4.5.1 Skip XML parsing for MDF4 files

MDF4 uses the XML channel comment to define the channel's display name (this acts as an alias for the channel name). XML parsing is an expensive operation that can have a big impact on the loading performance of measurements with high channel count.

You can use the keyword only argument *use_display_names* when creating MDF objects to control the XML parsing (default is *False*). This means that the display names will not be available when calling the *get* method.

5.1 Working with MDF

```
from asammdf import MDF, Signal
import numpy as np

# create 3 Signal objects

timestamps = np.array([0.1, 0.2, 0.3, 0.4, 0.5], dtype=np.float32)

# uint8
s_uint8 = Signal(samples=np.array([0, 1, 2, 3, 4], dtype=np.uint8),
                  timestamps=timestamps,
                  name='Uint8_Signal',
                  unit='u1')

# int32
s_int32 = Signal(samples=np.array([-20, -10, 0, 10, 20], dtype=np.int32),
                  timestamps=timestamps,
                  name='Int32_Signal',
                  unit='i4')

# float64
s_float64 = Signal(samples=np.array([-20, -10, 0, 10, 20], dtype=np.float64),
                    timestamps=timestamps,
                    name='Float64_Signal',
                    unit='f8')

# create empty MDF version 4.00 file
with MDF(version='4.10') as mdf4:

    # append the 3 signals to the new file
    signals = [s_uint8, s_int32, s_float64]
    mdf4.append(signals, comment='Created by Python')
```

(continues on next page)

(continued from previous page)

```

# save new file
mdf4.save('my_new_file.mf4', overwrite=True)

# convert new file to mdf version 3.10
mdf3 = mdf4.convert(version='3.10')
print(mdf3.version)

# get the float signal
sig = mdf3.get('Float64_Signal')
print(sig)

# cut measurement from 0.3s to end of measurement
mdf4_cut = mdf4.cut(start=0.3)
mdf4_cut.get('Float64_Signal').plot()

# cut measurement from start of measurement to 0.4s
mdf4_cut = mdf4.cut(stop=0.45)
mdf4_cut.get('Float64_Signal').plot()

# filter some signals from the file
mdf4 = mdf4.filter(['Int32_Signal', 'UInt8_Signal'])

# save using zipped transpose deflate blocks
mdf4.save('out.mf4', compression=2, overwrite=True)

```

5.2 Working with Signal

```

from asammdf import Signal
import numpy as np

# create 3 Signal objects with different time stamps

# uint8 with 100ms time raster
timestamps = np.array([0.1 * t for t in range(5)], dtype=np.float32)
s_uint8 = Signal(samples=np.array([t for t in range(5)], dtype=np.uint8),
                  timestamps=timestamps,
                  name='UInt8_Signal',
                  unit='u1')

# int32 with 50ms time raster
timestamps = np.array([0.05 * t for t in range(10)], dtype=np.float32)
s_int32 = Signal(samples=np.array(list(range(-500, 500, 100)), dtype=np.int32),
                  timestamps=timestamps,
                  name='Int32_Signal',
                  unit='i4')

# float64 with 300ms time raster
timestamps = np.array([0.3 * t for t in range(3)], dtype=np.float32)
s_float64 = Signal(samples=np.array(list(range(2000, -1000, -1000)), dtype=np.int32),
                   timestamps=timestamps,
                   name='Float64_Signal',
                   unit='f8')

```

(continues on next page)

(continued from previous page)

```

# map signals
xs = np.linspace(-1, 1, 50)
ys = np.linspace(-1, 1, 50)
X, Y = np.meshgrid(xs, ys)
vals = np.linspace(0, 180. / np.pi, 100)
phi = np.ones((len(vals), 50, 50), dtype=np.float64)
for i, val in enumerate(vals):
    phi[i] *= val
R = 1 - np.sqrt(X**2 + Y**2)
samples = np.cos(2 * np.pi * X + phi) * R

timestamps = np.arange(0, 2, 0.02)

s_map = Signal(samples=samples,
                timestamps=timestamps,
                name='Variable Map Signal',
                unit='dB')
s_map.plot()

prod = s_float64 * s_uint8
prod.name = 'Uint8_Signal * Float64_Signal'
prod.unit = '*'
prod.plot()

pow2 = s_uint8 ** 2
pow2.name = 'Uint8_Signal ^ 2'
pow2.unit = 'u1^2'
pow2.plot()

allsum = s_uint8 + s_int32 + s_float64
allsum.name = 'Uint8_Signal + Int32_Signal + Float64_Signal'
allsum.unit = '+'
allsum.plot()

# inplace operations
pow2 *= -1
pow2.name = '- Uint8_Signal ^ 2'
pow2.plot()

# cut signal
s_int32.plot()
cut_signal = s_int32.cut(start=0.2, stop=0.35)
cut_signal.plot()

```

5.3 MF4 demo file generator

```

from asammdf import MDF, SUPPORTED_VERSIONS, Signal
import numpy as np

cycles = 100
sigs = []

```

(continues on next page)

(continued from previous page)

```

mdf = MDF()

t = np.arange(cycles, dtype=np.float64)

# no conversion
sig = Signal(
    np.ones(cycles, dtype=np.uint64),
    t,
    name='Channel_no_conversion',
    unit='s',
    conversion=None,
    comment='Unsigned 64 bit channel {}',
)
sigs.append(sig)

# linear
conversion = {
    'a': 2,
    'b': -0.5,
}
sig = Signal(
    np.ones(cycles, dtype=np.int64),
    t,
    name='Channel_linear_conversion',
    unit='Nm',
    conversion=conversion,
    comment='Signed 64bit channel with linear conversion',
)
sigs.append(sig)

# algebraic
conversion = {
    'formula': '2 * sin(X)',
}
sig = Signal(
    np.arange(cycles, dtype=np.int32) / 100.0,
    t,
    name='Channel_algebraic',
    unit='eV',
    conversion=conversion,
    comment='Sinus channel with algebraic conversion',
)
sigs.append(sig)

# rational
conversion = {
    'P1': 0,
    'P2': 4,
    'P3': -0.5,
    'P4': 0,
    'P5': 0,
    'P6': 1,
}
sig = Signal(
    np.ones(cycles, dtype=np.int64),
    t,

```

(continues on next page)

(continued from previous page)

```

    name='Channel_rational_conversion',
    unit='Nm',
    conversion=conversion,
    comment='Channel with rational conversion',
)
sigs.append(sig)

# string channel
sig = [
    'String channel sample {}'.format(j).encode('ascii')
    for j in range(cycles)
]
sig = Signal(
    np.array(sig),
    t,
    name='Channel_string',
    comment='String channel',
    encoding='latin-1',
)
sigs.append(sig)

# byte array
ones = np.ones(cycles, dtype=np.dtype('(8,)u1'))
sig = Signal(
    ones*111,
    t,
    name='Channel_bytearray',
    comment='Byte array channel',
)
sigs.append(sig)

# tabular
vals = 20
conversion = {
    'raw_{}'.format(i): i
    for i in range(vals)
}
conversion.update(
    {
        'phys_{}'.format(i): -i
        for i in range(vals)
    }
)
sig = Signal(
    np.arange(cycles, dtype=np.uint32) % 20,
    t,
    name='Channel_tabular',
    unit='-',
    conversion=conversion,
    comment='Tabular channel',
)
sigs.append(sig)

# value to text
vals = 20
conversion = {
    'val_{}'.format(i): i

```

(continues on next page)

(continued from previous page)

```

    for i in range(vals)
}
conversion.update(
    {
        'text_{}'.format(i): 'key_{}'.format(i).encode('ascii')
        for i in range(vals)
    }
)
conversion['default'] = b'default key'
sig = Signal(
    np.arange(cycles, dtype=np.uint32) % 30,
    t,
    name='Channel_value_to_text',
    conversion=conversion,
    comment='Value to text channel',
)
sigs.append(sig)

# tabular with range
vals = 20
conversion = {
    'lower_{}'.format(i): i * 10
    for i in range(vals)
}
conversion.update(
    {
        'upper_{}'.format(i): (i + 1) * 10
        for i in range(vals)
    }
)
conversion.update(
    {
        'phys_{}'.format(i): i
        for i in range(vals)
    }
)
conversion['default'] = -1
sig = Signal(
    2 * np.arange(cycles, dtype=np.float64),
    t,
    name='Channel_value_range_to_value',
    unit='order',
    conversion=conversion,
    comment='Value range to value channel',
)
sigs.append(sig)

# value range to text
vals = 20
conversion = {
    'lower_{}'.format(i): i * 10
    for i in range(vals)
}
conversion.update(
    {
        'upper_{}'.format(i): (i + 1) * 10
        for i in range(vals)
    }
)

```

(continues on next page)

(continued from previous page)

```

    }
)
conversion.update(
    {
        'text_{}'.format(i): 'Level {}'.format(i)
        for i in range(vals)
    }
)
conversion['default'] = b'Unknown level'
sig = Signal(
    6 * np.arange(cycles, dtype=np.uint64) % 240,
    t,
    name='Channel_value_range_to_text',
    conversion=conversion,
    comment='Value range to text channel',
)
sigs.append(sig)

mdf.append(sigs, comment='single dimensional channels', common_timebase=True)

sigs = []

# lookup tabel with axis
samples = [
    np.ones((cycles, 2, 3), dtype=np.uint64) * 1,
    np.ones((cycles, 2), dtype=np.uint64) * 2,
    np.ones((cycles, 3), dtype=np.uint64) * 3,
]

types = [
    ('Channel_lookup_with_axis', '(2, 3)<u8'),
    ('channel_axis_1', '(2, )<u8'),
    ('channel_axis_2', '(3, )<u8'),
]

sig = Signal(
    np.core.records.fromarrays(samples, dtype=np.dtype(types)),
    t,
    name='Channel_lookup_with_axis',
    unit='A',
    comment='Array channel with axis',
)
sigs.append(sig)

# lookup tabel with default axis
samples = [
    np.ones((cycles, 2, 3), dtype=np.uint64) * 4,
]

types = [
    ('Channel_lookup_with_default_axis', '(2, 3)<u8'),
]

sig = Signal(

```

(continues on next page)

(continued from previous page)

```

    np.core.records.fromarrays(samples, dtype=np.dtype(types)),
    t,
    name='Channel_lookup_with_default_axis',
    unit='mA',
    comment='Array channel with default axis',
)
sigs.append(sig)

# structure channel composition
samples = [
    np.ones(cycles, dtype=np.uint8) * 10,
    np.ones(cycles, dtype=np.uint16) * 20,
    np.ones(cycles, dtype=np.uint32) * 30,
    np.ones(cycles, dtype=np.uint64) * 40,
    np.ones(cycles, dtype=np.int8) * -10,
    np.ones(cycles, dtype=np.int16) * -20,
    np.ones(cycles, dtype=np.int32) * -30,
    np.ones(cycles, dtype=np.int64) * -40,
]

types = [
    ('struct_channel_0', np.uint8),
    ('struct_channel_1', np.uint16),
    ('struct_channel_2', np.uint32),
    ('struct_channel_3', np.uint64),
    ('struct_channel_4', np.int8),
    ('struct_channel_5', np.int16),
    ('struct_channel_6', np.int32),
    ('struct_channel_7', np.int64),
]

sig = Signal(
    np.core.records.fromarrays(samples, dtype=np.dtype(types)),
    t,
    name='Channel_structure_composition',
    comment='Structure channel composition',
)
sigs.append(sig)

# nested structures
l4_arr = [
    np.ones(cycles, dtype=np.float64) * 41,
    np.ones(cycles, dtype=np.float64) * 42,
    np.ones(cycles, dtype=np.float64) * 43,
    np.ones(cycles, dtype=np.float64) * 44,
]

types = [
    ('level41', np.float64),
    ('level42', np.float64),
    ('level43', np.float64),
    ('level44', np.float64),
]

l4_arr = np.core.records.fromarrays(l4_arr, dtype=types)

```

(continues on next page)

(continued from previous page)

```
l3_arr = [
    l4_arr,
    l4_arr,
    l4_arr,
]

types = [
    ('level131', l4_arr.dtype),
    ('level132', l4_arr.dtype),
    ('level133', l4_arr.dtype),
]

l3_arr = np.core.records.fromarrays(l3_arr, dtype=types)

l2_arr = [
    l3_arr,
    l3_arr,
]

types = [
    ('level121', l3_arr.dtype),
    ('level122', l3_arr.dtype),
]

l2_arr = np.core.records.fromarrays(l2_arr, dtype=types)

l1_arr = [
    l2_arr,
]

types = [
    ('level111', l2_arr.dtype),
]

l1_arr = np.core.records.fromarrays(l1_arr, dtype=types)

sigs.append(
    Signal(
        l1_arr,
        t,
        name='Nested_structures',
    )
)

mdf.append(sigs, comment='arrays', common_timebase=True)

mdf.save('demo.mf4', overwrite=True)
```


6.1 Test setup

The benchmarks were done using two test files (available [here](#)) (for mdf version 3 and 4) of around 170MB. The files contain 183 data groups and a total of 36424 channels.

asamdf 5.22.0 was compared against *mdfreader* 4.1.

For each category two aspect were noted: elapsed time and peak RAM usage.

6.1.1 Dependencies

You will need the following packages to be able to run the benchmark script

- psutil
- mdfreader

6.1.2 Usage

Extract the test files from the archive, or provide a folder that contains the files “test.mdf” and “test.mf4”. Run the module *bench.py* (see `–help` option for available options)

6.2 x64 Python results

Benchmark environment

- 3.7.4 (tags/v3.7.4:e09359112e, Jul 8 2019, 20:34:20) [MSC v.1916 64 bit (AMD64)]
- Windows-10-10.0.18362-SP0
- Intel64 Family 6 Model 158 Stepping 10, GenuineIntel

- numpy 1.19.1
- 16GB installed RAM

Notations used in the results

- compress = mdfreader mdf object created with compression=blosc
- nodata = mdfreader mdf object read with no_data_loading=True

Files used for benchmark:

- **mdf version 3.10**
 - 167 MB file size
 - 183 groups
 - 36424 channels
- **mdf version 4.00**
 - 183 MB file size
 - 183 groups
 - 36424 channels

Open file	Time [ms]	RAM [MB]
asammdf 5.22.0 mdfv3	277	135
mdfreader 4.1 mdfv3	1564	451
mdfreader 4.1 no_data_loading mdfv3	706	204
mdfreader 4.1 compress mdfv3	1403	319
asammdf 5.22.0 mdfv4	432	147
mdfreader 4.1 mdfv4	4084	483
mdfreader 4.1 no_data_loading mdfv4	2966	270
mdfreader 4.1 compress mdfv4	3835	355



Save file	Time [ms]	RAM [MB]
asammdf 5.22.0 mdfv3	395	134
mdfreader 4.1 mdfv3	4056	479
mdfreader 4.1 no_data_loading mdfv3	4818	542
mdfreader 4.1 compress mdfv3	4313	479
asammdf 5.22.0 mdfv4	374	147
mdfreader 4.1 mdfv4	2270	502
mdfreader 4.1 no_data_loading mdfv4	3424	578
mdfreader 4.1 compress mdfv4	2475	497







Get all channels (36424 calls)	Time [ms]	RAM [MB]
asammdf 5.22.0 mdfv3	3978	136
mdfreader 4.1 mdfv3	46	451
mdfreader 4.1 nodata mdfv3	11929	241
mdfreader 4.1 compress mdfv3	166	319
asammdf 5.22.0 mdfv4	7060	147
mdfreader 4.1 mdfv4	60	483
mdfreader 4.1 nodata mdfv4	17991	303
mdfreader 4.1 compress mdfv4	173	356


Convert file	Time [ms]	RAM [MB]
asammdf 5.22.0 v3 to v4	2749	192
asammdf 5.22.0 v4 to v410	2239	177
asammdf 5.22.0 v4 to v420	2611	216

Merge 3 files	Time [ms]	RAM [MB]
asammdf 5.22.0 v3	7604	202
mdfreader 4.1 v3	0*	0*
mdfreader 4.1 nodata v3	0*	0*
mdfreader 4.1 compress v3	0*	0*
asammdf 5.22.0 v4	6990	206
mdfreader 4.1 v4	32816	1123
mdfreader 4.1 nodata v4	32998	1229
mdfreader 4.1 compress v4	32908	1118

6.2.1 Graphical results







With the GUI tool you can

- visualize channels
- compare channels from multiple files in the same plot
- see channel, conversion and source metadata as stored in the MDF file
- access library functionality for single files (convert, export, cut, filter, resample, scramble) and multiple files (concatenate, stack)

After you pip install asammdf using `pip install asammdf[gui]` there will be a new script called *asammdf.exe* in the *python_installation_folder\Scripts* folder.

The following dependencies are required by the GUI

- PyQt5
- pyqtgraph

7.1 General shortcuts

Shortcut	Action	Description
F1	Help	Opens this online help page
F2	Create plot	Create a new Plot window using the checked channels from the selection tree
F3	Create numeric	Create a new Numeric window using the checked channels from the selection tree
F4	Create tabular	Create a new Tabular window using the checked channels from the selection tree
F8	Toggle fullscreen	In the single files mode will display the current opened file in full screen
Ctrl+O	Open file(s)	

7.2 Menu

7.2.1 File

The first menu command is *Open*. Depending on the mode this allows to open files individually or for batch processing.

The second menu command is *Open folder*. If this is selected then, starting with the selected root folder, all sub-folders are searched recursively for MDF files.

Once a file has been opened, the user can load or save a display configuration using the *Open configuration* and *Save configuration* menu items.

7.2.2 Mode

- *Single files* : files are opened individually
- *Batch processing* : allows processing multiple files
- *Comparison* : show channels from all the opened files

7.2.3 Settings

The following settings are available

- **Sub-plots**: controls if multiple subplots will be created when the plot button is pressed
 - Disabled: a single plot is used that is overwritten
 - Enabled: a new subplot is added
- **Link sub-plots X-axis**: controls the subplots are linked on the X axis (zooming will affect all sub-plots)
 - Disabled
 - Enabled
- **Ignore value2text conversions**: do not apply the value to text conversions
 - Disabled
 - Enabled
- **Plot background**: switch plot background color (does not affect existing plots)
 - Black
 - White
- **Plot X axis**: select how the X axis will be displayed
 - **seconds**
 - * `time` : values will be formatted as hours, minutes and seconds
 - `date` : the values will use the measurement start datetime
- **Theme**: switch application theme
 - Dark
 - Light

- **Integer interpolation:** selects the way integer channels are interpolated
 - 0 - repeat previous sample
 - 1 - linear interpolation
 - 2 - hybrid interpolation

The settings are saved and restored each time the GUI is started.

7.2.4 Plot

There are several keyboard shortcuts for handling the plots:

Shortcut	Action	Description
C	Cursor	Displays a movable cursor that will trigger the display of the current value for all plot channels
F	Fit	Y-axis fit all active channels on the screen, keeping the current X-axis range
G	Grid	Toggle grid lines
H	Home	XY-axis fit all active channels
I	Zoom-in	X-axis zoom-in ¹
O	Zoom-out	X-axis zoom-out ¹
X	Zoom to range	If the region is enabled, it will zoom to it
M	Statistics	Toggle the display of the statistic panel
R	Range	Display a movable range that will trigger the display of the delta values for all plot channels ²
S	Stack	Y Stack all active channels so that they don't overlap, keeping the X-axis range
Y	Lock/unlock region	Lock or unlock the left margin of the region
.	Toggle dots	Toggle the display of signal samples (using dots affects performance)
←	Move cursor left	Moves the cursor to the next sample on the left
→	Move cursor right	Moves the cursor to the next sample on the right
Ins	Insert computation	Insert new channel in the plot using functions and operations
F8	Toggle full screen	In the single files mode will display the current opened file in full screen
Alt+I	Toggle trigger texts	Toggle the text boxes for the triggers ⁶
Alt+R	Raw samples	Toggle raw samples mode for the selected channels ⁶
Alt+S	Scaled samples	Toggle scaled (physical) samples mode for the selected channels

Continued on next page

Table 1 – continued from previous page

Shortcut	Action	Description
Ctrl+B	Bin	Toggle binary representation of integer channels
Ctrl+H	Hex	Toggle hex representation of integer channels
Ctrl+I	Insert cursor comment	Insert a visual vertical line and comment at the current cursor position ⁶
Ctrl+P	Physical	Toggle physical representation of integer channels
Ctrl+S	Save plot channels	Save channels from current active subplot in a new MF4 file
Ctrl+Shift+S	Save all channels	Save all channels from all sub-plots in a new MF4 file
Shift+C	Cascade sub-plots	Cascade the sub plots
Shift+F	Toggle frames	Will toggle the sub plots MDI window frames
Shift+L	Toggle channel list	Will toggle the channel tree for the current opened file
Shift+T	Tile sub-plots	Tiles sub-plots in a grid
Shift+V	Tile vertically	Tiles sub-plots vertically ³
Shift+H	Tile horizontally	Tiles sub-plots horizontally ³

7.3 Single files

The *Single files* page is used to open several files individually for visualization and processing (for example exporting to csv or hdf5).


¹ If the cursor is present then zooming will center on it.

² Clicking the plot will move the left margin of the region. Pressing CTRL while clicking the plot will move the right margin of the region.

⁶ New in *asammdf* 5.20.0

³ New in *asammdf* 5.7.0

7.3.1 Layout elements



1. Opened files tabs
2. Channel tree display mode
3. Complete channels tree
4. Command buttons
5. Plot/Sub-plots area
6. Numeric window
7. Plot window
8. Sub-plot channel selection list
9. Sub-plot graphics area
10. Sub-plot channels statistics panel
11. File operations

7.3.1.1 1. Opened files tabs

In the single files mode, you can open multiple files in parallel. The tab names have the title set to the short file name, and the complete file path can be seen as the tab tool-tip.

There is no restriction, so the same file can be opened several times.

7.3.1.2 2. Channel tree display mode

The channel tree can be displayed in two ways


- as a naturally sorted list

- grouped using the internal file structure

7.3.1.3 3. Complete channels tree

This tree contains all the channels found in the measurement.

Double clicking a channel name will display a pop-up window with the channel information (CNBLOCK, CCBLOCK and SIBLOCK/CEBLOCK)




Only the channels that are checked in the channels tree will be selected for plotting when the *Plot* button is pressed. Checking or unchecking channels will not affect the current plot or sub-plots.

7.3.1.4 4. Command buttons

From left to right the buttons have the following functionality

- **Load configuration:** restores channels tree and all sub-plot windows from a saved configuration file
- **Save configuration:** saves all sub-plots (channels, colors, common axis and enable state) and channel tree
- **Select all channels:** checks all channels in the channels tree
- **Reset selection:** unchecks all channels in the channels tree
- **Advanced search & select:** will open an advanced search dialog
 - the dialog can use wildcard and regex patterns
 - multiple channels can be selected, and thus checked in the channels tree
 - in the “Pattern based window” tab the user can define a pattern that will be used to filter out the channels from the measurement file, and as a second filtering step some condition can be used based on the channels values. This information will be saved in the window configuration. The pattern based windows can be easily recognized by the title bar icon



- **Add window:** generates a new window (Numeric, Plot or Tabular) based on the current checked channels from the channels tree. If sub-plots are disabled in the settings then the current window is replaced by the new plot. If sub-plots are enabled then a new sub-plot will be added, and the already existing sub-plots will not be affected. The same channel can be used in multiple sub-plots.

7.3.1.5 5. Plot/Sub-plots area

If sub-plots are enabled then multiple plots can be used. The sub-plots can be re-arranged using drag & drop.

7.3.1.6 6. Numeric window

Numeric windows can handle a lot more channels than plot windows. You can use a numeric window to see the channel values at certain time stamps. The time stamps can be selected using the spin box or the slider.

7.3.1.7 7. Plot window

Plot windows are used to graphically display the channel samples. *pyqtgraph* is used for the plots; to get the best performance consider the following tips

- limit the number of channels: plotting hundreds of channels can get really slow
- disabling dots will make the plots a lot more responsive

7.3.1.8 8. Sub-plot channel selection list

When the *Plot* button is pressed the checked channels will populate the *Selected channels list*.

Selecting items from the *Selected channels list* will display their Y-axis on the left side of the plot. Individual axis for each signal can also be toggled and they will show on the right side of the plot.

It is also necessary to select a single item when the *Statistics* panel is active to compute the statistics for the item's channel.




Each item has five elements

1. display enable checkbox
2. color select button
3. channel name and unit label
4. channel value label⁴
5. common axis checkbox
6. individual axis checkbox⁵

The channel name can be copied to the clipboard using Ctrl+C.


Double clicking an item will open a range editor dialog



Here we can specify a range value visual alert. When the cursor is active and the current channel value is within the specified range, the item background will change to the selected color.

⁴ the value is only displayed if the cursor or range are active. For the cursor is will show the current value, and for the range it will show the value delta between the range start and stop timestamps

⁵ New in *asammdf* 5.7.0




7.3.1.9 9. Sub-plot graphics area

The initial plot will have all channels homed (see the *H* keyboard shortcut)


The cursor is toggled using the *C* keyboard shortcut, and with it the channel values will be displayed for each item in the *Selected channels list*. The cursor can also be invoked by clicking the plot area.

The *Ctrl+H* and *Ctrl+B* keyboard shortcuts will


- change the axis values for integer channels to hex and bin mode
- change the channel value display mode for each integer channel item in the *Selected channels list*



Using the *R* keyboard shortcut will toggle the range, and with it the channel values will be displayed for each item in the *Selected channels* list. When the range is enabled, using the *H* keyboard shortcut will not home to the whole time range, but instead will use the range time interval.



The *Statistics* panel is toggle using the *M* keyboard shortcut



You can insert new computed channels by pressing the *insert* key. This will allow either to compute basic operations using the plot channels, or to apply a function on one of the plot channels.

+ Define new channel
?
X


Computation

ASAM.M.SCALAR.SLONG.IDENTICAL
+ (add)
ASAM.M.SCALAR.SWORD.IDENTICAL
SUM_CHANNEL
u
Apply

Function

channel name
channel unit
Apply

Cancel



The currently active plot's channels can be saved to a new file by pressing *Ctrl+S*. The channels from all sub-plots can be saved to a new file by pressing *Ctrl+Shift+S*.


The sub-plots can be tiled as a grid, vertically or horizontally

7.3.2 Drag & Drop

Channels can be dragged and dropped between sub-plots for easier configuration.

7.4 Multiple files

The *Multiple files* toolbox page is used to concatenate or stack multiple files.



The files list can be rearranged in the list (1) by drag and dropping lines. Unwanted files can be deleted by selecting them and pressing the *DEL* key. The files order is considered from top to bottom.

7.5 Comparison

Use *CTRL+F* to search channels from all the opened files. The channel names are prefixed with the measurement index.

CHAPTER 8

Indices and tables

- `genindex`
- `modindex`
- `search`

A

`astype()` (*asammdf.signal.Signal* method), 62

`AttachmentBlock` (class in *asammdf.blocks.v4_blocks*), 50

C

`Channel` (class in *asammdf.blocks.v2_v3_blocks*), 31

`Channel` (class in *asammdf.blocks.v4_blocks*), 51

`ChannelConversion` (class in *asammdf.blocks.v2_v3_blocks*), 33

`ChannelConversion` (class in *asammdf.blocks.v4_blocks*), 53

`ChannelDependency` (class in *asammdf.blocks.v2_v3_blocks*), 34

`ChannelExtension` (class in *asammdf.blocks.v2_v3_blocks*), 35

`ChannelGroup` (class in *asammdf.blocks.v2_v3_blocks*), 35

`ChannelGroup` (class in *asammdf.blocks.v4_blocks*), 55

`cleanup_timestamps()` (*asammdf.mdf.MDF* method), 8

`concatenate()` (*asammdf.mdf.MDF* static method), 8

`convert()` (*asammdf.mdf.MDF* method), 9

`copy()` (*asammdf.signal.Signal* method), 62

`cut()` (*asammdf.mdf.MDF* method), 9

`cut()` (*asammdf.signal.Signal* method), 62

D

`DataBlock` (class in *asammdf.blocks.v4_blocks*), 56

`DataGroup` (class in *asammdf.blocks.v2_v3_blocks*), 36

`DataGroup` (class in *asammdf.blocks.v4_blocks*), 55

`DataList` (class in *asammdf.blocks.v4_blocks*), 56

E

`EventBlock` (class in *asammdf.blocks.v4_blocks*), 60

`export()` (*asammdf.mdf.MDF* method), 10

`extend()` (*asammdf.signal.Signal* method), 63

`extract()` (*asammdf.blocks.v4_blocks.AttachmentBlock* method), 51

`extract_bus_logging()` (*asammdf.mdf.MDF* method), 11

F

`FileHistory` (class in *asammdf.blocks.v4_blocks*), 59

`FileIdentificationBlock` (class in *asammdf.blocks.v2_v3_blocks*), 37

`FileIdentificationBlock` (class in *asammdf.blocks.v4_blocks*), 57

`filter()` (*asammdf.mdf.MDF* method), 12

G

`get_group()` (*asammdf.mdf.MDF* method), 13

H

`HeaderBlock` (class in *asammdf.blocks.v2_v3_blocks*), 37

`HeaderBlock` (class in *asammdf.blocks.v4_blocks*), 57

I

`interp()` (*asammdf.signal.Signal* method), 63

`iter_channels()` (*asammdf.mdf.MDF* method), 14

`iter_get()` (*asammdf.mdf.MDF* method), 14

`iter_groups()` (*asammdf.mdf.MDF* method), 15

`iter_to_dataframe()` (*asammdf.mdf.MDF* method), 15

M

`MDF` (class in *asammdf.mdf*), 7

P

`physical()` (*asammdf.signal.Signal* method), 64

`plot()` (*asammdf.signal.Signal* method), 64

`ProgramBlock` (class in *asammdf.blocks.v2_v3_blocks*), 38

R

`resample()` (*asammdf.mdf.MDF method*), [17](#)

S

`scramble()` (*asammdf.mdf.MDF static method*), [19](#)

`select()` (*asammdf.mdf.MDF method*), [20](#)

`Signal` (*class in asammdf.signal*), [61](#)

`SourceInformation` (*class in asammdf.blocks.v4_blocks*), [58](#)

`stack()` (*asammdf.mdf.MDF static method*), [21](#)

`start_time` (*asammdf.blocks.v4_blocks.HeaderBlock attribute*), [58](#)

`start_time` (*asammdf.mdf.MDF attribute*), [22](#)

T

`TextBlock` (*class in asammdf.blocks.v2_v3_blocks*), [39](#)

`TextBlock` (*class in asammdf.blocks.v4_blocks*), [59](#)

`to_dataframe()` (*asammdf.mdf.MDF method*), [22](#)

`TriggerBlock` (*class in asammdf.blocks.v2_v3_blocks*), [39](#)

V

`validate()` (*asammdf.signal.Signal method*), [64](#)

W

`whereis()` (*asammdf.mdf.MDF method*), [23](#)